

Standard Document Classes for L^AT_EX version 2e*

Copyright (C) 1992 by Leslie Lamport
Copyright (C) 1994-97 by Frank Mittelbach Johannes Braams

2005/09/16

Contents

1 The DOCSTRIP modules	2
2 Initial Code	3
3 Declaration of Options	3
3.1 Setting Paper Sizes	3
3.2 Choosing the type size	4
3.3 Two-side or one-side printing	4
3.4 Draft option	4
3.5 Titlepage option	4
3.6 openright option	4
3.7 Twocolumn printing	5
3.8 Equation numbering on the left	5
3.9 Flush left displays	5
3.10 Open bibliography	5
4 Executing Options	5
5 Loading Packages	6
6 Document Layout	6
6.1 Fonts	6
6.2 Paragraphing	8
6.3 Page Layout	9
6.3.1 Vertical spacing	10
6.3.2 The dimension of text	10
6.3.3 Margins	12
6.3.4 Footnotes	14
6.3.5 Float placement parameters	14
6.4 Page Styles	16
6.4.1 Marking conventions	17
6.4.2 Defining the page styles	17
7 Document Markup	19
7.1 The title	19
7.2 Chapters and Sections	21
7.2.1 Building blocks	21
7.2.2 Mark commands	22
7.2.3 Define Counters	22
7.2.4 Front Matter, Main Matter, and Back Matter	23
7.2.5 Parts	24

*This file has version number v1.4f, last revised 2005/09/16.

7.2.6	Chapters	26
7.2.7	Lower level headings	28
7.3	Lists	29
7.3.1	General List Parameters	29
7.3.2	Enumerate	31
7.3.3	Itemize	31
7.3.4	Description	31
7.4	Defining new environments	32
7.4.1	Abstract	32
7.4.2	Verse	32
7.4.3	Quotation	32
7.4.4	Quote	33
7.4.5	Theorem	33
7.4.6	Titlepage	33
7.4.7	Appendix	34
7.5	Setting parameters for existing environments	34
7.5.1	Array and tabular	34
7.5.2	Tabbing	35
7.5.3	Minipage	35
7.5.4	Framed boxes	35
7.5.5	Equation and eqnarray	35
7.6	Floating objects	35
7.6.1	Figure	36
7.6.2	Table	36
7.6.3	Captions	37
7.7	Font changing	38
8	Cross Referencing	38
8.1	Table of Contents, etc.	38
8.1.1	Table of Contents	39
8.1.2	List of figures	41
8.1.3	List of tables	42
8.2	Bibliography	42
8.3	The index	43
8.4	Footnotes	44
9	Initialization	45
9.1	Words	45
9.2	Date	45
9.3	Two column mode	45
9.4	The page style	46
9.5	Single or double sided printing	46

1 The DOCSTRIP modules

The following modules are used in the implementation to direct DOCSTRIP in generating the external files:

article	produce the documentclass article
report	produce the documentclass report
size10	produce the class option for 10pt
size11	produce the class option for 11pt
size12	produce the class option for 12pt
book	produce the documentclass book
bk10	produce the book class option for 10pt
bk11	produce the book class option for 11pt
bk12	produce the book class option for 12pt
driver	produce a documentation driver file

2 Initial Code

In this part we define a few commands that are used later on.

- \@ptsize This control sequence is used to store the second digit of the pointsize we are typesetting in. So, normally, its value is one of 0, 1 or 2.
- 1 `(*article | report | book)`
 - 2 `\newcommand{\@ptsize}{}`
- \if@restonecol When the document has to be printed in two columns, we sometimes have to temporarily switch to one column. This switch is used to remember to switch back.
- 3 `\newif\if@restonecol`
- \if@titlepage A switch to indicate if a titlepage has to be produced. For the article document class the default is not to make a separate titlepage.
- 4 `\newif\if@titlepage`
 - 5 `{article}\@titlepagefalse`
 - 6 `{!article}\@titlepagetrue`
- \if@openright A switch to indicate if chapters must start on a right-hand page. The default for the report class is no; for the book class it's yes.
- 7 `{!article}\newif\if@openright`
- \if@mainmatter The switch \if@mainmatter, only available in the document class book, indicates whether we are processing the main material in the book.
- 8 `{book}\newif\if@mainmatter \@mainmattertrue`

3 Declaration of Options

3.1 Setting Paper Sizes

The variables \paperwidth and \paperheight should reflect the physical paper size after trimming. For desk printer output this is usually the real paper size since there is no post-processing. Classes for real book production will probably add other paper sizes and additionally the production of crop marks for trimming. In compatibility mode, these (and some of the subsequent) options are disabled, as they were not present in L^AT_EX2.09.

- 9 `\if@compatibility\else`
- 10 `\DeclareOption{a4paper}`
- 11 `{\setlength{\paperheight}{297mm}}%`
- 12 `\setlength{\paperwidth}{210mm}}`
- 13 `\DeclareOption{a5paper}`
- 14 `{\setlength{\paperheight}{210mm}}%`
- 15 `\setlength{\paperwidth}{148mm}}`
- 16 `\DeclareOption{b5paper}`
- 17 `{\setlength{\paperheight}{250mm}}%`
- 18 `\setlength{\paperwidth}{176mm}}`
- 19 `\DeclareOption{letterpaper}`
- 20 `{\setlength{\paperheight}{11in}}%`
- 21 `\setlength{\paperwidth}{8.5in}}`
- 22 `\DeclareOption{legalpaper}`
- 23 `{\setlength{\paperheight}{14in}}%`
- 24 `\setlength{\paperwidth}{8.5in}}`
- 25 `\DeclareOption{executivepaper}`
- 26 `{\setlength{\paperheight}{10.5in}}%`
- 27 `\setlength{\paperwidth}{7.25in}}`

The option `landscape` switches the values of \paperheight and \paperwidth, assuming the dimensions were given for portrait paper.

- 28 `\DeclareOption{landscape}`

```

29   {\setlength{\tempdima} {\paperheight}%
30   \setlength{\paperheight} {\paperwidth}%
31   \setlength{\paperwidth} {\tempdima}%
32 \fi

```

3.2 Choosing the type size

The type size options are handled by defining `\@ptsize` to contain the last digit of the size in question and branching on `\ifcase` statements. This is done for historical reasons to stay compatible with other packages that use the `\@ptsize` variable to select special actions. It makes the declarations of size options less than 10pt difficult, although one can probably use 9 and 8 assuming that a class wont define both 8pt and 18pt options.

```

33 \if@compatibility
34   \renewcommand{\@ptsize}{0}
35 \else
36 \DeclareOption{10pt}{\renewcommand{\@ptsize}{0}}
37 \fi
38 \DeclareOption{11pt}{\renewcommand{\@ptsize}{1}}
39 \DeclareOption{12pt}{\renewcommand{\@ptsize}{2}}

```

3.3 Two-side or one-side printing

For two-sided printing we use the switch `\if@twoside`. In addition we have to set the `\if@mparswitch` to get any margin paragraphs into the outside margin.

```

40 \if@compatibility\else
41 \DeclareOption{oneside}{\@twosidefalse \mparswitchfalse}
42 \fi
43 \DeclareOption{twoside}{\@twosidetrue \mparswitchtrue}

```

3.4 Draft option

If the user requests `draft` we show any overfull boxes. We could probably add some more interesting stuff to this option.

```

44 \DeclareOption{draft}{\setlength{\overfullrule}{5pt}}
45 \if@compatibility\else
46 \DeclareOption{final}{\setlength{\overfullrule}{0pt}}
47 \fi

```

3.5 Titlepage option

An article usually has no separate titlepage, but the user can request one.

```

48 \DeclareOption{titlepage}{\@titlepagetrue}
49 \if@compatibility\else
50 \DeclareOption{notitlepage}{\@titlepagefalse}
51 \fi

```

3.6 openright option

This option determines whether or not a chapter must start on a right-hand page request one.

```

52 \if@compatibility
53 <book> \openrighttrue
54 \else
55 \DeclareOption{openright}{\openrighttrue}
56 \DeclareOption{openany}{\openrightfalse}
57 \fi

```

3.7 Twocolumn printing

Two-column and one-column printing is again realized via a switch.

```
58 \if@compatibility\else
59 \DeclareOption{onecolumn}{\@twocolumnfalse}
60 \fi
61 \DeclareOption{twocolumn}{\@twocolumntrue}
```

3.8 Equation numbering on the left

The option `leqno` can be used to get the equation numbers on the left side of the equation. It loads code which is generated automatically from the kernel files when the format is built. If the equation number does get a special formatting then instead of using the kernel file the class would need to provide the code explicitly.

```
62 \DeclareOption{leqno}{\input{leqno.clo}}
```

3.9 Flush left displays

The option `fleqn` redefines the displayed math environments in such a way that they come out flush left, with an indentation of `\mathindent` from the prevailing left margin. It loads code which is generated automatically from the kernel files when the format is built.

```
63 \DeclareOption{fleqn}{\input{fleqn.clo}}
```

3.10 Open bibliography

The option `openbib` produces the “open” bibliography style, in which each block starts on a new line, and succeeding lines in a block are indented by `\bibindent`.

```
64 \DeclareOption{openbib}{%
```

First some hook into the bibliography environment is filled.

```
65   \AtEndOfPackage{%
66     \renewcommand{\openbib@code}{%
67       \advance\leftmargin\@bibindent
68       \itemindent -\@bibindent
69       \listparindent \itemindent
70       \parsep \z@}
71   }%
```

In addition the definition of `\newblock` is overwritten.

```
72   \renewcommand{\newblock}{\par}%
73 }
```

4 Executing Options

Here we execute the default options to initialize certain variables. Note that the document class ‘book’ always uses two sided printing.

```
74 <*article>
75 \ExecuteOptions{letterpaper,10pt,oneside,onecolumn,final}
76 </article>
77 <*report>
78 \ExecuteOptions{letterpaper,10pt,oneside,onecolumn,final,openany}
79 </report>
80 <*book>
81 \ExecuteOptions{letterpaper,10pt,twoside,onecolumn,final,openright}
82 </book>
```

The `\ProcessOptions` command causes the execution of the code for every option FOO which is declared and for which the user typed the FOO option in his `\documentclass` command. For every option BAR he typed, which is not declared, the option is assumed to be a global option. All options will be passed as document options to any `\usepackage` command in the document preamble.

83 `\ProcessOptions`

Now that all the options have been executed we can load the chosen class option file that contains all size dependent code.

```
84 {!book}\input{size1\@ptsize.clo}
85 {book}\input{bk1\@ptsize.clo}
86 {/article | report | book}
```

5 Loading Packages

The standard class files do not load additional packages.

6 Document Layout

In this section we are finally dealing with the nasty typographical details.

6.1 Fonts

L^AT_EX offers the user commands to change the size of the font, relative to the ‘main’ size. Each relative size changing command `\size` executes the command `\@setfontsize\size<font-size>\baselineskip` where:

`<font-size>` The absolute size of the font to use from now on.

`<baselineskip>` The normal value of `\baselineskip` for the size of the font selected. (The actual value will be `\baselinestretch * <baselineskip>`.)

A number of commands, defined in the L^AT_EX kernel, shorten the following definitions and are used throughout. They are:

<code>\@vpt</code>	5	<code>\@vipt</code>	6	<code>\@viipt</code>	7
<code>\@viiipt</code>	8	<code>\@ixpt</code>	9	<code>\@xpt</code>	10
<code>\@xipt</code>	10.95	<code>\@xiipt</code>	12	<code>\@xivpt</code>	14.4
...					

`\normalsize` The user level command for the main size is `\normalsize`. Internally L^AT_EX uses `\@normalsize` when it refers to the main size. `\@normalsize` will be defined to work like `\normalsize` if the latter is redefined from its default definition (that just issues an error message). Otherwise `\@normalsize` simply selects a 10pt/12pt size.

The `\normalsize` macro also sets new values for `\abovedisplayskip`, `\abovedisplayshortskip` and `\belowdisplayshortskip`.

```
87 {*10pt | 11pt | 12pt}
88 \renewcommand\normalsize{%
89 {*10pt}
90   \@setfontsize\normalsize\@xpt\@xiipt
91   \abovedisplayskip 10\p@ \oplus2\p@ \minus5\p@
92   \abovedisplayshortskip \z@ \oplus3\p@
93   \belowdisplayshortskip 6\p@ \oplus3\p@ \minus3\p@
94 {/10pt}
95 {*11pt}
96   \@setfontsize\normalsize\@xipt{13.6}%
97   \abovedisplayskip 11\p@ \oplus3\p@ \minus6\p@
98   \abovedisplayshortskip \z@ \oplus3\p@}
```

```

99      \belowdisplayshortskip 6.5\p@ \oplus3.5\p@ \ominus3\p@
100   </11pt>
101   <*12pt>
102     @setfontsize\normalsize\xipt{14.5}%
103     \abovedisplayskip 12\p@ \oplus3\p@ \ominus7\p@
104     \abovedisplayshortskip \z@ \oplus3\p@
105     \belowdisplayshortskip 6.5\p@ \oplus3.5\p@ \ominus3\p@
106   </12pt>

```

The `\belowdisplayskip` is always equal to the `\abovedisplayskip`. The parameters of the first level list are always given by `\@listI`.

```

107     \belowdisplayskip \abovedisplayskip
108     \let\@listi\@listI}

```

We initially choose the `\normalsize` font.

```
109 \normalsize
```

`\small` This is similar to `\normalsize`.

```

110 \newcommand\small{%
111   <*10pt>
112     @setfontsize\small\xipt{11}%
113     \abovedisplayskip 8.5\p@ \oplus3\p@ \ominus4\p@
114     \abovedisplayshortskip \z@ \oplus2\p@
115     \belowdisplayshortskip 4\p@ \oplus2\p@ \ominus2\p@
116     \def\@listi{\leftmargin\leftmargini
117                 \topsep 4\p@ \oplus2\p@ \ominus2\p@
118                 \parsep 2\p@ \oplus\p@ \ominus\p@
119                 \itemsep \parsep}%
120   </10pt>
121   <*11pt>
122     @setfontsize\small\xipt{12}%
123     \abovedisplayskip 10\p@ \oplus2\p@ \ominus5\p@
124     \abovedisplayshortskip \z@ \oplus3\p@
125     \belowdisplayshortskip 6\p@ \oplus3\p@ \ominus3\p@
126     \def\@listi{\leftmargin\leftmargini
127                 \topsep 6\p@ \oplus2\p@ \ominus2\p@
128                 \parsep 3\p@ \oplus2\p@ \ominus\p@
129                 \itemsep \parsep}%
130   </11pt>
131   <*12pt>
132     @setfontsize\small\xipt{13.6}%
133     \abovedisplayskip 11\p@ \oplus3\p@ \ominus6\p@
134     \abovedisplayshortskip \z@ \oplus3\p@
135     \belowdisplayshortskip 6.5\p@ \oplus3.5\p@ \ominus3\p@
136     \def\@listi{\leftmargin\leftmargini
137                 \topsep 9\p@ \oplus3\p@ \ominus5\p@
138                 \parsep 4.5\p@ \oplus2\p@ \ominus\p@
139                 \itemsep \parsep}%
140   </12pt>
141     \belowdisplayskip \abovedisplayskip
142 }

```

`\footnotesize` This is similar to `\normalsize`.

```

143 \newcommand\footnotesize{%
144   <*10pt>
145     @setfontsize\footnotesize\xipt{9.5}%
146     \abovedisplayskip 6\p@ \oplus2\p@ \ominus4\p@
147     \abovedisplayshortskip \z@ \oplus\p@
148     \belowdisplayshortskip 3\p@ \oplus\p@ \ominus2\p@
149     \def\@listi{\leftmargin\leftmargini
150                 \topsep 3\p@ \oplus\p@ \ominus\p@
151                 \parsep 2\p@ \oplus\p@ \ominus\p@
152                 \itemsep \parsep}%

```

```

153 </10pt>
154 <*11pt>
155   \@setfontsize\footnotesize\@ixipt{11}%
156   \abovedisplayskip 8\p@ \oplus2\p@ \minus4\p@
157   \abovedisplayshortskip \z@ \oplus\p@
158   \belowdisplayshortskip 4\p@ \oplus2\p@ \minus2\p@
159   \def\@listi{\leftmargin\leftmargini
160     \topsep 4\p@ \oplus2\p@ \minus2\p@
161     \parsep 2\p@ \oplus\p@ \minus\p@
162     \itemsep \parsep}%
163 </11pt>
164 <*12pt>
165   \@setfontsize\footnotesize\@xipt\@xiipt
166   \abovedisplayskip 10\p@ \oplus2\p@ \minus5\p@
167   \abovedisplayshortskip \z@ \oplus3\p@
168   \belowdisplayshortskip 6\p@ \oplus3\p@ \minus3\p@
169   \def\@listi{\leftmargin\leftmargini
170     \topsep 6\p@ \oplus2\p@ \minus2\p@
171     \parsep 3\p@ \oplus2\p@ \minus\p@
172     \itemsep \parsep}%
173 </12pt>
174   \belowdisplayskip \abovedisplayskip
175 }
176 </10pt | 11pt | 12pt>

```

\scriptsize These are all much simpler than the previous macros, they just select a new fontsize, but leave the parameters for displays and lists alone.

```

\tiny
\large
\Large
\LARGE
\huge
\Huge
177 <*10pt>
178 \newcommand\scriptsize{\@setfontsize\scriptsize\@viipt\@viiipt}
179 \newcommand\tiny{\@setfontsize\tiny\@vpt\@vpt}
180 \newcommand\large{\@setfontsize\large\@xiipt{14}}
181 \newcommand\Large{\@setfontsize\Large\@xivpt{18}}
182 \newcommand\LARGE{\@setfontsize\LARGE\@xviipt{22}}
183 \newcommand\huge{\@setfontsize\huge\@xxpt{25}}
184 \newcommand\Huge{\@setfontsize\Huge\@xxvpt{30}}
185 </10pt>
186 <*11pt>
187 \newcommand\scriptsize{\@setfontsize\scriptsize\@viiipt{9.5}}
188 \newcommand\tiny{\@setfontsize\tiny\@vpt\@vpt}
189 \newcommand\large{\@setfontsize\large\@xiipt{14}}
190 \newcommand\Large{\@setfontsize\Large\@xivpt{18}}
191 \newcommand\LARGE{\@setfontsize\LARGE\@xviipt{22}}
192 \newcommand\huge{\@setfontsize\huge\@xxpt{25}}
193 \newcommand\Huge{\@setfontsize\Huge\@xxvpt{30}}
194 </11pt>
195 <*12pt>
196 \newcommand\scriptsize{\@setfontsize\scriptsize\@viiipt{9.5}}
197 \newcommand\tiny{\@setfontsize\tiny\@vpt\@vpt}
198 \newcommand\large{\@setfontsize\large\@xivpt{18}}
199 \newcommand\Large{\@setfontsize\Large\@xviipt{22}}
200 \newcommand\LARGE{\@setfontsize\LARGE\@xxpt{25}}
201 \newcommand\huge{\@setfontsize\huge\@xxvpt{30}}
202 \let\Huge=\huge
203 </12pt>

```

6.2 Paragraphing

\lineskip
\normallineskip These parameters control TeX's behaviour when two lines tend to come too close together.

```

204 <article | report | book>
205 \setlength\lineskip{1\p@}
206 \setlength\normallineskip{1\p@}

```

<code>\baselinestretch</code>	This is used as a multiplier for <code>\baselineskip</code> . The default is to <i>not</i> stretch the baselines. Note that if this command doesn't resolve to "empty" any plus or minus part in the specification of <code>\baselineskip</code> is ignored.
	207 <code>\renewcommand\baselinestretch{}</code>
<code>\parskip</code> <code>\parindent</code>	<code>\parskip</code> gives extra vertical space between paragraphs and <code>\parindent</code> is the width of the paragraph indentation. The value of <code>\parindent</code> depends on whether we are in two column mode.
	208 <code>\setlength\parskip{0\p@ \oplus \p@}</code> 209 <code></article report book></code> 210 <code>{*10pt 11pt 12pt}</code> 211 <code>\if@twocolumn</code> 212 <code>\setlength\parindent{1em}</code> 213 <code>\else</code> 214 <code>{10pt} \setlength\parindent{15\p@}</code> 215 <code>{11pt} \setlength\parindent{17\p@}</code> 216 <code>{12pt} \setlength\parindent{1.5em}</code> 217 <code>\fi</code> 218 <code>{/10pt 11pt 12pt}</code>
<code>\smallskipamount</code> <code>\medskipamount</code> <code>\bigskipamount</code>	The values for these three parameters are set in the L ^A T _E X kernel. They should perhaps vary, according to the size option specified. But as they have always had the same value regardless of the size option we do not change them to stay compatible with both L ^A T _E X 2.09 and older releases of L ^A T _E X 2 _{ε} .
	219 <code>{*10pt 11pt 12pt}</code> 220 <code>\setlength\smallskipamount{3\p@ \oplus 1\p@ \ominus 1\p@}</code> 221 <code>\setlength\medskipamount{6\p@ \oplus 2\p@ \ominus 2\p@}</code> 222 <code>\setlength\bigskipamount{12\p@ \oplus 4\p@ \ominus 4\p@}</code> 223 <code>{/10pt 11pt 12pt}</code>
<code>\@lowpenalty</code> <code>\@medpenalty</code> <code>\@highpenalty</code>	The commands <code>\nopagebreak</code> and <code>\nolinebreak</code> put in penalties to discourage these breaks at the point they are put in. They use <code>\@lowpenalty</code> , <code>\@medpenalty</code> or <code>\@highpenalty</code> , dependent on their argument.
	224 <code></article report book></code> 225 <code>\@lowpenalty 51</code> 226 <code>\@medpenalty 151</code> 227 <code>\@highpenalty 301</code>
<code>\clubpenalty</code> <code>\widowpenalty</code>	These penalties are use to discourage club and widow lines. Because we use their default values we only show them here, commented out.
	228 % <code>\clubpenalty 150</code> 229 % <code>\widowpenalty 150</code>
<code>\displaywidowpenalty</code> <code>\predisplaypenalty</code> <code>\postdisplaypenalty</code>	Discourage (but not so much) widows in front of a math display and forbid breaking directly in front of a display. Allow break after a display without a penalty. Again the default values are used, therefore we only show them here.
	230 % <code>\displaywidowpenalty 50</code> 231 % <code>\predisplaypenalty 10000</code> 232 % <code>\postdisplaypenalty 0</code>
<code>\interlinepenalty</code>	Allow the breaking of a page in the middle of a paragraph.
	233 % <code>\interlinepenalty 0</code>
<code>\brokenpenalty</code>	We allow the breaking of a page after a hyphenated line.
	234 % <code>\brokenpenalty 100</code> 235 <code></article report book></code>

6.3 Page Layout

All margin dimensions are measured from a point one inch from the top and lefthand side of the page.

6.3.1 Vertical spacing

\headheight	The \headheight is the height of the box that will contain the running head. The \headsep is the distance between the bottom of the running head and the top of the text. The \topskip is the \baselineskip for the first line on a page; L ^A T _E X's output routine will not work properly if it has the value 0pt, so do not do that!
	<pre> 236 {<10pt 11pt 12pt} 237 \setlength\headheight{12\p@} 238 {!bk}\setlength\headsep {25\p@} 239 {10pt & bk}\setlength\headsep {.25in} 240 {11pt & bk}\setlength\headsep {.275in} 241 {12pt & bk}\setlength\headsep {.275in} 242 {10pt}\setlength\topskip {10\p@} 243 {11pt}\setlength\topskip {11\p@} 244 {12pt}\setlength\topskip {12\p@} </pre>
\footskip	The distance from the baseline of the box which contains the running footer to the baseline of last line of text is controlled by the \footskip.
	<pre> 245 {!bk}\setlength\footskip{30\p@} 246 {10pt & bk}\setlength\footskip{.35in} 247 {11pt & bk}\setlength\footskip{.38in} 248 {12pt & bk}\setlength\footskip{30\p@} </pre>

\maxdepth The T_EX primitive register \maxdepth has a function that is similar to that of \topskip. The register \cmaxdepth should always contain a copy of \maxdepth. This is achieved by setting it internally at \begin{document}. In both plain T_EX and L^AT_EX 2.09 \maxdepth had a fixed value of 4pt; in native L^AT_EX2e mode we let the value depend on the typesize. We set it so that \maxdepth + \topskip = typesize \times 1.5. As it happens, in these classes \topskip is equal to the typesize, therefore we set \maxdepth to half the value of \topskip.

```

249 \if@compatibility \setlength\maxdepth{4\p@} \else
250 \setlength\maxdepth{.5\topskip} \fi

```

6.3.2 The dimension of text

\textwidth	When we are in compatibility mode we have to make sure that the dimensions of the printed area are not different from what the user was used to see.
------------	--

```

251 \if@compatibility
252   \if@twocolumn
253     \setlength\textwidth{410\p@}
254   \else
255 {10pt&!bk}   \setlength\textwidth{345\p@}
256 {11pt&!bk}   \setlength\textwidth{360\p@}
257 {12pt&!bk}   \setlength\textwidth{390\p@}
258 {10pt & bk}  \setlength\textwidth{4.5in}
259 {11pt & bk}  \setlength\textwidth{5in}
260 {12pt & bk}  \setlength\textwidth{5in}
261 \fi

```

When we are not in compatibility mode we can set some of the dimensions differently, taking into account the paper size for instance.

```
262 \else
```

First, we calculate the maximum \textwidth, which we will allow on the selected paper and store it in \ctempdima. Then we store the length of a line with approximately 60–70 characters in \ctempdimb. The values given are more or less suitable when Computer Modern fonts are used.

```

263 \setlength\ctempdima{\paperwidth}
264 \addtolength\ctempdima{-2in}
265 {10pt} \setlength\ctempdimb{345\p@}
266 {11pt} \setlength\ctempdimb{360\p@}
267 {12pt} \setlength\ctempdimb{390\p@}

```

Now we can set the `\textwidth`, depending on whether we will be setting one or two columns.

In two column mode each *column* shouldn't be wider than `\@tempdimb` (which could happen on A3 paper for instance).

```

268  \if@twocolumn
269    \ifdim\@tempdima>2\@tempdimb\relax
270      \setlength\textwidth{2\@tempdimb}
271    \else
272      \setlength\textwidth{\@tempdima}
273    \fi

```

In one column mode the text should not be wider than the minimum of the paperwidth (minus 2 inches for the margins) and the maximum length of a line as defined by the number of characters.

```

274  \else
275    \ifdim\@tempdima>\@tempdimb\relax
276      \setlength\textwidth{\@tempdimb}
277    \else
278      \setlength\textwidth{\@tempdima}
279    \fi
280  \fi
281 \fi

```

Here we modify the width of the text a little to be a whole number of points.

```

282 \if@compatibility\else
283   \@settopoint\textwidth
284 \fi

```

`\textheight` Now that we have computed the width of the text, we have to take care of the height. The `\textheight` is the height of text (including footnotes and figures, excluding running head and foot).

First make sure that the compatibility mode gets the same dimensions as we had with L^AT_EX2.09. The number of lines was calculated as the floor of the old `\textheight` minus `\topskip`, divided by `\baselineskip` for `\normalsize`. The old value of `\textheight` was 528pt.

```

285 \if@compatibility
286 <10pt&!bk> \setlength\textheight{43\baselineskip}
287 <10pt & bk> \setlength\textheight{41\baselineskip}
288 <11pt> \setlength\textheight{38\baselineskip}
289 <12pt> \setlength\textheight{36\baselineskip}

```

Again we compute this, depending on the papersize and depending on the `\baselineskip` that is used, in order to have a whole number of lines on the page.

```

290 \else
291   \setlength\@tempdima{\paperheight}

```

We leave at least a 1 inch margin on the top and the bottom of the page.

```
292 \addtolength\@tempdima{-2in}
```

We also have to leave room for the running headers and footers.

```
293 \addtolength\@tempdima{-1.5in}
```

Then we divide the result by the current `\baselineskip` and store this in the count register `\@tempcnta`, which then contains the number of lines that fit on this page.

```

294 \divide\@tempdima\baselineskip
295 \@tempcnta=\@tempdima

```

From this we can calculate the height of the text.

```

296 \setlength\textheight{\@tempcnta\baselineskip}
297 \fi

```

The first line on the page has a height of `\topskip`.

```
298 \addtolength\textheight{\topskip}
```

6.3.3 Margins

Most of the values of these parameters are now calculated, based on the papersize in use. In the calcluations the `\marginparsep` needs to be taken into account so we give it its value first.

`\marginparsep`
`\marginparpush` The horizontal space between the main text and marginal notes is determined by `\marginparsep`, the minimum vertical separation between two marginal notes is controlled by `\marginparpush`.

```

299 \if@twocolumn
300 \setlength\marginparsep {10\p@}
301 \else
302 <10pt&!bk> \setlength\marginparsep{11\p@}
303 <11pt&!bk> \setlength\marginparsep{10\p@}
304 <12pt&!bk> \setlength\marginparsep{10\p@}
305 <bk> \setlength\marginparsep{7\p@}
306 \fi
307 <10pt | 11pt>\setlength\marginparpush{5\p@}
308 <12pt>\setlength\marginparpush{7\p@}
```

Now we can give the values for the other margin parameters. For native L^AT_EX 2 _{ϵ} , these are calculated.

`\oddsidemargin` First we give the values for the compatibility mode.

Values for two-sided printing:

```

309 \if@compatibility
310 <*bk>
311 <10pt> \setlength\oddsidemargin { .5in}
312 <11pt> \setlength\oddsidemargin { .25in}
313 <12pt> \setlength\oddsidemargin { .25in}
314 <10pt> \setlength\evensidemargin {1.5in}
315 <11pt> \setlength\evensidemargin {1.25in}
316 <12pt> \setlength\evensidemargin {1.25in}
317 <10pt> \setlength\marginparwidth { .75in}
318 <11pt> \setlength\marginparwidth {1in}
319 <12pt> \setlength\marginparwidth {1in}
320 </bk>
321 <*!bk>
322 \if@twoside
323 <10pt> \setlength\oddsidemargin {44\p@}
324 <11pt> \setlength\oddsidemargin {36\p@}
325 <12pt> \setlength\oddsidemargin {21\p@}
326 <10pt> \setlength\evensidemargin {82\p@}
327 <11pt> \setlength\evensidemargin {74\p@}
328 <12pt> \setlength\evensidemargin {59\p@}
329 <10pt> \setlength\marginparwidth {107\p@}
330 <11pt> \setlength\marginparwidth {100\p@}
331 <12pt> \setlength\marginparwidth {85\p@}
```

Values for one-sided printing:

```

332 \else
333 <10pt> \setlength\oddsidemargin {63\p@}
334 <11pt> \setlength\oddsidemargin {54\p@}
335 <12pt> \setlength\oddsidemargin {39.5\p@}
336 <10pt> \setlength\evensidemargin {63\p@}
337 <11pt> \setlength\evensidemargin {54\p@}
338 <12pt> \setlength\evensidemargin {39.5\p@}
339 <10pt> \setlength\marginparwidth {90\p@}
340 <11pt> \setlength\marginparwidth {83\p@}
341 <12pt> \setlength\marginparwidth {68\p@}
342 \fi
343 </!bk>
```

And values for two column mode:

```

344  \if@twocolumn
345    \setlength\oddsidemargin {30\p0}
346    \setlength\evensidemargin {30\p0}
347    \setlength\marginparwidth {48\p0}
348  \fi

```

When we are not in compatibility mode we can take the dimensions of the selected paper into account.

The values for `\oddsidemargin` and `\marginparwidth` will be set depending on the status of the `\if@twoside`.

If `@twoside` is true (which is always the case for book) we make the inner margin smaller than the outer one.

```

349 \else
350  \if@twoside
351    \setlength\@tempdima      {\paperwidth}
352    \addtolength\@tempdima   {-\textwidth}
353    \setlength\oddsidemargin {.4\@tempdima}
354    \addtolength\oddsidemargin {-1in}

```

The width of the margin for text is set to the remainder of the width except for a ‘real margin’ of white space of width 0.4in. A check should perhaps be built in to ensure that the (text) margin width does not get too small!

```

355  \setlength\marginparwidth  {.6\@tempdima}
356  \addtolength\marginparwidth {-\marginparsep}
357  \addtolength\marginparwidth {-0.4in}

```

For one-sided printing we center the text on the page, by calculating the difference between `\textwidth` and `\paperwidth`. Half of that difference is than used for the margin (thus `\oddsidemargin` is 1in less).

```

358 \else
359  \setlength\@tempdima      {\paperwidth}
360  \addtolength\@tempdima   {-\textwidth}
361  \setlength\oddsidemargin {-.5\@tempdima}
362  \addtolength\oddsidemargin {-1in}
363  \setlength\marginparwidth {-.5\@tempdima}
364  \addtolength\marginparwidth {-\marginparsep}
365  \addtolength\marginparwidth {-0.4in}
366  \addtolength\marginparwidth {-0.4in}
367 \fi

```

With the above algorithm the `\marginparwidth` can come out quite large which we may not want.

```

368  \ifdim \marginparwidth >2in
369    \setlength\marginparwidth{2in}
370  \fi

```

Having done these calculations we make them pt values.

```

371  \@settopoint\oddsidemargin
372  \@settopoint\marginparwidth

```

The `\evensidemargin` can now be computed from the values set above.

```

373  \setlength\evensidemargin  {\paperwidth}
374  \addtolength\evensidemargin{-2in}
375  \addtolength\evensidemargin{-\textwidth}
376  \addtolength\evensidemargin{-\oddsidemargin}

```

Setting `\evensidemargin` to a full point value may produce a small error. However it will lie within the error range a doublesided printer of today’s technology can accurately print.

```

377  \@settopoint\evensidemargin
378 \fi

```

`\topmargin` The `\topmargin` is the distance between the top of ‘the printable area’—which is 1 inch below the top of the paper—and the top of the box which contains the running head.

It can now be computed from the values set above.

```

379 \if@compatibility
380 <!bk> \setlength{\topmargin}{27pt}
381 <10pt & bk> \setlength{\topmargin}{.75in}
382 <11pt & bk> \setlength{\topmargin}{.73in}
383 <12pt & bk> \setlength{\topmargin}{.73in}
384 \else
385   \setlength{\topmargin}{\paperheight}
386   \addtolength{\topmargin}{-2in}
387   \addtolength{\topmargin}{-\headheight}
388   \addtolength{\topmargin}{-\headsep}
389   \addtolength{\topmargin}{-\textheight}
390   \addtolength{\topmargin}{-\footskip}    % this might be wrong!

```

By changing the factor in the next line the complete page can be shifted vertically.

```

391   \addtolength{\topmargin}{-.5\topmargin}
392   \settowidth{\topmargin}
393 \fi

```

6.3.4 Footnotes

`\footnotesep` `\footnotesep` is the height of the strut placed at the beginning of every footnote. It equals the height of a normal `\footnoterule` strut in this class, thus no extra space occurs between footnotes.

```

394 <10pt> \setlength{\footnotesep}{6.65\p@}
395 <11pt> \setlength{\footnotesep}{7.7\p@}
396 <12pt> \setlength{\footnotesep}{8.4\p@}

```

`\footins` `\skip\footins` is the space between the last line of the main text and the top of the first footnote.

```

397 <10pt> \setlength{\skip\footins}{9\p@ \oplus 4\p@ \ominus 2\p@}
398 <11pt> \setlength{\skip\footins}{10\p@ \oplus 4\p@ \ominus 2\p@}
399 <12pt> \setlength{\skip\footins}{10.8\p@ \oplus 4\p@ \ominus 2\p@}
400 </10pt | 11pt | 12pt>

```

6.3.5 Float placement parameters

All float parameters are given default values in the L^AT_EX 2_ε kernel. For this reason parameters that are not counters need to be set with `\renewcommand`.

Limits for the placement of floating objects

`\c@topnumber` The *topnumber* counter holds the maximum number of floats that can appear on the top of a text page.

```

401 <article | report | book>
402 \setcounter{topnumber}{2}

```

`\topfraction` This indicates the maximum part of a text page that can be occupied by floats at the top.

```
403 \renewcommand{\topfraction}{.7}
```

`\c@bottomnumber` The *bottomnumber* counter holds the maximum number of floats that can appear on the bottom of a text page.

```
404 \setcounter{bottomnumber}{1}
```

`\bottomfraction` This indicates the maximum part of a text page that can be occupied by floats at the bottom.

```
405 \renewcommand{\bottomfraction}{.3}
```

<code>\c@totalnumber</code>	This indicates the maximum number of floats that can appear on any text page. 406 <code>\setcounter{totalnumber}{3}</code>
<code>\textfraction</code>	This indicates the minimum part of a text page that has to be occupied by text. 407 <code>\renewcommand\textfraction{.2}</code>
<code>\floatpagefraction</code>	This indicates the minimum part of a page that has to be occupied by floating objects before a ‘float page’ is produced. 408 <code>\renewcommand\floatpagefraction{.5}</code>
<code>\cdbltopnumber</code>	The <i>dbltopnumber</i> counter holds the maximum number of two column floats that can appear on the top of a two column text page. 409 <code>\setcounter{dbltopnumber}{2}</code>
<code>\dbltopfraction</code>	This indicates the maximum part of a two column text page that can be occupied by two column floats at the top. 410 <code>\renewcommand\dbltopfraction{.7}</code>
<code>\dblfloatpagefraction</code>	This indicates the minimum part of a page that has to be occupied by two column wide floating objects before a ‘float page’ is produced. 411 <code>\renewcommand\dblfloatpagefraction{.5}</code> 412 <code></article report book></code>

Floats on a text page

<code>\floatsep</code>	When a floating object is placed on a page with text, these parameters control the separation between the float and the other objects on the page. These parameters are used for both one-column mode and single-column floats in two-column mode.
<code>\textfloatsep</code>	<code>\floatsep</code> is the space between adjacent floats that are moved to the top or bottom of the text page.
<code>\intextsep</code>	<code>\textfloatsep</code> is the space between the main text and floats at the top or bottom of the page.
	<code>\intextsep</code> is the space between in-text floats and the text.
413 <code><*10pt></code>	
414 <code>\setlength\floatsep {12\p@ \oplus 2\p@ \ominus 2\p@}</code>	
415 <code>\setlength\textfloatsep{20\p@ \oplus 2\p@ \ominus 4\p@}</code>	
416 <code>\setlength\intextsep {12\p@ \oplus 2\p@ \ominus 2\p@}</code>	
417 <code></10pt></code>	
418 <code><*11pt></code>	
419 <code>\setlength\floatsep {12\p@ \oplus 2\p@ \ominus 2\p@}</code>	
420 <code>\setlength\textfloatsep{20\p@ \oplus 2\p@ \ominus 4\p@}</code>	
421 <code>\setlength\intextsep {12\p@ \oplus 2\p@ \ominus 2\p@}</code>	
422 <code></11pt></code>	
423 <code><*12pt></code>	
424 <code>\setlength\floatsep {12\p@ \oplus 2\p@ \ominus 4\p@}</code>	
425 <code>\setlength\textfloatsep{20\p@ \oplus 2\p@ \ominus 4\p@}</code>	
426 <code>\setlength\intextsep {14\p@ \oplus 4\p@ \ominus 4\p@}</code>	
427 <code></12pt></code>	

<code>\dblfloatsep</code>	When floating objects that span the whole <code>\textwidth</code> are placed on a text page when we are in <code>twocolumn</code> mode the separation between the float and the text is controlled by <code>\dblfloatsep</code> and <code>\dbltextfloatsep</code> .
<code>\dbltextfloatsep</code>	<code>\dblfloatsep</code> is the space between adjacent floats that are moved to the top or bottom of the text page.

`\dbltextfloatsep` is the space between the main text and floats at the top or bottom of the page.

```
428 <*10pt>
429 \setlength\dblfloatsep {12\p@ \oplus 2\p@ \ominus 2\p@}
430 \setlength\dbltextfloatsep{20\p@ \oplus 2\p@ \ominus 4\p@}
```

```

431 </10pt>
432 <*11pt>
433 \setlength\dblfloatsep {12\p@ \oplus 2\p@ \ominus 2\p@}
434 \setlength\dbltextfloatsep{20\p@ \oplus 2\p@ \ominus 4\p@}
435 </11pt>
436 <*12pt>
437 \setlength\dblfloatsep {14\p@ \oplus 2\p@ \ominus 4\p@}
438 \setlength\dbltextfloatsep{20\p@ \oplus 2\p@ \ominus 4\p@}
439 </12pt>

```

Floats on their own page or column

\@fptop When floating objects are placed on separate pages the layout of such pages is controlled by these parameters. At the top of the page \@fptop amount of stretchable whitespace is inserted, at the bottom of the page we get an \@fpbot amount of stretchable whitespace. Between adjacent floats the \@fpsep is inserted.

These parameters are used for the placement of floating objects in one column mode, or in single column floats in two column mode.

Note that at least one of the two parameters \@fptop and \@fpbot should contain a plus ...fil to allow filling the remaining empty space.

```

440 <*10pt>
441 \setlength\fptop{0\p@ \oplus 1fil}
442 \setlength\fpsep{8\p@ \oplus 2fil}
443 \setlength\fpbot{0\p@ \oplus 1fil}
444 </10pt>
445 <*11pt>
446 \setlength\fptop{0\p@ \oplus 1fil}
447 \setlength\fpsep{8\p@ \oplus 2fil}
448 \setlength\fpbot{0\p@ \oplus 1fil}
449 </11pt>
450 <*12pt>
451 \setlength\fptop{0\p@ \oplus 1fil}
452 \setlength\fpsep{10\p@ \oplus 2fil}
453 \setlength\fpbot{0\p@ \oplus 1fil}
454 </12pt>

```

\@dblftop Double column floats in two column mode are handled with similar parameters.

```

455 <*10pt>
456 \setlength\dblftop{0\p@ \oplus 1fil}
457 \setlength\dblpsep{8\p@ \oplus 2fil}
458 \setlength\dblfpbot{0\p@ \oplus 1fil}
459 </10pt>
460 <*11pt>
461 \setlength\dblftop{0\p@ \oplus 1fil}
462 \setlength\dblpsep{8\p@ \oplus 2fil}
463 \setlength\dblfpbot{0\p@ \oplus 1fil}
464 </11pt>
465 <*12pt>
466 \setlength\dblftop{0\p@ \oplus 1fil}
467 \setlength\dblpsep{10\p@ \oplus 2fil}
468 \setlength\dblfpbot{0\p@ \oplus 1fil}
469 </12pt>
470 <*article | report | book>

```

6.4 Page Styles

The page style *foo* is defined by defining the command \ps@*foo*. This command should make only local definitions. There should be no stray spaces in the definition, since they could lead to mysterious extra spaces in the output (well, that's something that should be always avoided).

\@evenhead The \ps@... command defines the macros \@oddhead, \@oddfoot, \@evenhead, and \@evenfoot to define the running heads and feet—e.g., \@oddhead is the macro to produce the contents of the heading box for odd-numbered pages. It is called inside an \hbox of width \textwidth.

6.4.1 Marking conventions

To make headings determined by the sectioning commands, the page style defines the commands \chaptermark, \sectionmark, ..., where \chaptermark{<TEXT>} is called by \chapter to set a mark, and so on.

The \...mark commands and the \...head macros are defined with the help of the following macros. (All the \...mark commands should be initialized to no-ops.)

LATEX extends TEX's \mark facility by producing two kinds of marks, a 'left' and a 'right' mark, using the following commands:

\markboth{<LEFT>}{<RIGHT>}: Adds both marks.

\markright{<RIGHT>}: Adds a 'right' mark.

\leftmark: Used in the \@oddhead, \@oddfoot, \@evenhead or \@evenfoot macros, it gets the current 'left' mark. \leftmark works like TEX's \botmark command.

\rightmark: Used in the \@oddhead, \@oddfoot, \@evenhead or \@evenfoot macros, it gets the current 'right' mark. \rightmark works like TEX's \firstmark command.

The marking commands work reasonably well for right marks 'numbered within' left marks—e.g., the left mark is changed by a \chapter command and the right mark is changed by a \section command. However, it does produce somewhat anomalous results if two \markboth's occur on the same page.

Commands like \tableofcontents that should set the marks in some page styles use a \mkboth command, which is \let by the pagestyle command (\ps@...) to \markboth for setting the heading or to \@gobbletwo to do nothing.

6.4.2 Defining the page styles

The pagestyles *empty* and *plain* are defined in *latex.dtx*.

\ps@headings The definition of the page style *headings* has to be different for two sided printing than it is for one sided printing.

```
471 \if@twoside
472   \def\ps@headings{%
```

The running feet are empty in this page style, the running head contains the page number and one of the marks.

```
473     \let@\oddfoot@empty\let@\evenfoot@empty
474     \def@\evenhead{\thepage\hfil\slshape\leftmark}%
475     \def@\oddhead{\slshape\rightmark}\hfil\thepage}%
```

When using this page style, the contents of the running head is determined by the chapter and section titles. So we \let \mkboth to \markboth.

```
476     \let@\mkboth\markboth
```

For the article document class we define \sectionmark to clear the right mark and put the number of the section (when it is numbered) and its title in the left mark. The rightmark is set by \subsectionmark to contain the subsection titles.

Note the use of ##1 for the parameter of the \sectionmark command, which will be defined when \ps@headings is executed.

```
477 <*article>
478   \def\sectionmark##1{%
479     \markboth {\MakeUppercase{%
480       \ifnum \c@secnumdepth >\z@
```

```

481           \thesection\quad
482           \fi
483           ##1}}{}}
484   \def\subsectionmark##1{%
485     \markright {\%
486       \ifnum \c@secnumdepth >\@ne
487         \thesubsection\quad
488       \fi
489     ##1}}
490 
```

In the report and book document classes we use the `\chaptermark` and `\sectionmark` macros to fill the running heads.

Note the use of `##1` for the parameter of the `\chaptermark` command, which will be defined when `\ps@headings` is executed.

```

491 <*report | book>
492   \def\chaptermark##1{%
493     \markboth {\MakeUppercase{%
494       \ifnum \c@secnumdepth >\m@ne
495 <book>         \if@mainmatter
496           \chapapp\ \thechapter. \ %
497 <book>         \fi
498       \fi
499     ##1}}{}}
500   \def\sectionmark##1{%
501     \markright {\MakeUppercase{%
502       \ifnum \c@secnumdepth >\z@
503         \thesection. \ %
504       \fi
505     ##1}}{}}
506 
```

The definition of `\ps@headings` for one sided printing can be much simpler, because we treat even and odd pages the same. Therefore we don't need to define `\@even....`

```

507 \else
508   \def\ps@headings{%
509     \let\@oddfoot\@empty
510     \def\@oddhead{\rlap{\rightmark}\hfil\thepage}%
511     \let\@mkboth\markboth

```

We use `\markright` now instead of `\markboth` as we did for two sided printing.

```

512 <article>
513   \def\sectionmark##1{%
514     \markright {\MakeUppercase{%
515       \ifnum \c@secnumdepth >\m@ne
516         \thesection\quad
517       \fi
518     ##1}}{}}
519 
```

```

520 <*report | book>
521   \def\chaptermark##1{%
522     \markright {\MakeUppercase{%
523       \ifnum \c@secnumdepth >\m@ne
524 <book>         \if@mainmatter
525           \chapapp\ \thechapter. \ %
526 <book>         \fi
527       \fi
528     ##1}}{}}
529 
```

\ps@myheadings The definition of the page style *myheadings* is fairly simple because the user determines the contents of the running head himself by using the \markboth and \markright commands.

```
531 \def\ps@myheadings{%
532   \let\@oddfoot\@empty\let\@evenfoot\@empty
533   \def\@evenhead{\the\page\hfil\slshape\leftmark}%
534   \def\@oddhead{\slshape\rightmark}\hfil\the\page}%
```

We have to make sure that the marking commands that are used by the chapter and section headings are disabled. We do this \letting them to a macro that gobbles its argument(s).

```
535   \let\@mkboth\@gobbletwo
536 {!article} \let\chaptermark\@gobble
537   \let\sectionmark\@gobble
538 {article} \let\subsectionmark\@gobble
539 }
```

7 Document Markup

7.1 The title

\title \author \date These three macros are provided by *latex.dtx* to provide information about the title, author(s) and date of the document. The information is stored away in internal control sequences. It is the task of the \maketitle command to use the information provided. The definitions of these macros are shown here for information.

```
540 % \newcommand*{\title}[1]{\gdef\@title{\#1}}
541 % \newcommand*{\author}[1]{\gdef\@author{\#1}}
542 % \newcommand*{\date}[1]{\gdef\@date{\#1}}
```

The \date macro gets today's date by default.

```
543 % \date{\today}
```

\maketitle The definition of \maketitle depends on whether a separate title page is made. This is the default for the report and book document classes, but for the article class it is optional.

When we are making a title page, we locally redefine \footnotesize and footnoterule to change the appearance of the footnotes that are produced by the \thanks command; these changes affect all footnotes.

```
544 \if@titlepage
545 \newcommand\maketitle{\begin{titlepage}%
546 \let\footnotesize\small
547 \let\footnoterule\relax
548 \let\footnote\thanks}
```

We center the entire title vertically; the centering is set off a little by adding a \vskip. (In compatibility mode the pagenumber is set to 0 by the titlepage environment to keep the behaviour of L^AT_EX 2.09 style files.)

```
549 \null\vfil
550 \vskip 60\p@
```

Then we set the title, in a \LARGE font; leave a little space and set the author(s) in a \large font. We do this inside a tabular environment to get them in a single column. Before the date we leave a little whitespace again.

```
551 \begin{center}%
552 {\LARGE \@title \par}%
553 \vskip 3em%
554 {\large
555 \lineskip .75em%
556 \begin{tabular}[t]{c}%
557 \@author}
```

```

558      \end{tabular}\par}%
559      \vskip 1.5em%
560      {\large \@date \par}%
561      % Set date in \large size.
      \end{center}\par

```

Then we call `\@thanks` to print the information that goes into the footnote and finish the page.

```

562  \@thanks
563  \vfil\null
564  \end{titlepage}%

```

We reset the `footnote` counter, disable `\thanks` and `\maketitle` and save some storage space by emptying the internal information macros.

```

565  \setcounter{footnote}{0}%
566  \global\let\thanks\relax
567  \global\let\maketitle\relax
568  \global\let\@thanks\empty
569  \global\let\@author\empty
570  \global\let\@date\empty
571  \global\let\@title\empty

```

After the title is set the declaration commands `\title`, etc. can vanish. The definition of `\and` makes only sense within the argument of `\author` so this can go as well.

```

572  \global\let\title\relax
573  \global\let\author\relax
574  \global\let\date\relax
575  \global\let\and\relax
576 }

```

When the title is not on a page of its own, the layout of the title is a little different. We use symbols to mark the footnotes and we have to deal with two column documents.

Therefore we first start a new group to keep changes local. Then we redefine `\thefootnote` to use `\fnsymbol`; and change `\makefnmark` so that footnotemarks have zero width (to make the centering of the author names look better).

```

577 \else
578 \newcommand\maketitle{\par
579   \begingroup
580     \renewcommand\thefootnote{\fnsymbol{c@footnote}}%
581     \def\@makefnmark{\rlap{\textsuperscript{\normalfont\@thefnmark}}}%
582     \long\def\@makefntext{\parindent 1em\noindent
583       \hb@xt@1.8em{%
584         \hss\textsuperscript{\normalfont\@thefnmark}}}

```

If this is a twocolumn document we start a new page in twocolumn mode, with the title set to the full width of the text. The actual printing of the title information is left to `\maketitle`.

```

585  \if@twocolumn
586    \ifnum \col@number=\@ne
587      \@maketitle
588    \else
589      \twocolumn[\@maketitle]%
590    \fi
591  \else

```

When this is not a twocolumn document we just start a new page, prevent floating objects from appearing on the top of this page and print the title information.

```

592    \newpage
593    \global\@topnum\z@    % Prevents figures from going at top of page.
594    \@maketitle
595  \fi

```

This page gets a *plain* layout. We call `\@thanks` to produce the footnotes.

```

596  \thispagestyle{plain}\@thanks

```

Now we can close the group, reset the *footnote* counter, disable `\thanks`, `\maketitle` and `\@maketitle` and save some storage space by emptying the internal information macros.

```

597  \endgroup
598  \setcounter{footnote}{0}%
599  \global\let\thanks\relax
600  \global\let\maketitle\relax
601  \global\let@\maketitle\relax
602  \global\let@\thanks\@empty
603  \global\let@\author\@empty
604  \global\let@\date\@empty
605  \global\let@\title\@empty
606  \global\let\title\relax
607  \global\let\author\relax
608  \global\let\date\relax
609  \global\let\and\relax
610 }

```

- `\@maketitle` This macro takes care of formatting the title information when we have no separate title page.

We always start a new page, leave some white space and center the information. The title is set in a `\LARGE` font, the author names and the date in a `\large` font.

```

611 \def\@maketitle{%
612   \newpage
613   \null
614   \vskip 2em%
615   \begin{center}%
616     \let \footnote \thanks
617     {\LARGE \@title \par}%
618     \vskip 1.5em%
619     {\large
620       \lineskip .5em%
621       \begin{tabular}[t]{c}%
622         \@author
623       \end{tabular}\par}%
624     \vskip 1em%
625     {\large \@date}%
626   \end{center}%
627   \par
628   \vskip 1.5em}
629 \fi

```

7.2 Chapters and Sections

7.2.1 Building blocks

The definitions in this part of the class file make use of two internal macros, `\@startsection` and `\secdef`. To understand what is going on here, we describe their syntax.

The macro `\@startsection` has 6 required arguments, optionally followed by a *, an optional argument and a required argument:

$$\text{\@startsection}\langle name \rangle \langle level \rangle \langle indent \rangle \langle beforeskip \rangle \langle afterskip \rangle \langle style \rangle \text{ optional } * \\ [\langle altheading \rangle] \langle heading \rangle$$

It is a generic command to start a section, the arguments have the following meaning:

`\langle name \rangle` The name of the user level command, e.g., ‘section’.

`\langle level \rangle` A number, denoting the depth of the section – e.g., chapter=1, section = 2, etc. A section number will be printed if and only if `\langle level \rangle <=` the value of the `secnumdepth` counter.

<indent> The indentation of the heading from the left margin

<beforeskip> The absolute value of this argument gives the skip to leave above the heading. If it is negative, then the paragraph indent of the text following the heading is suppressed.

<afterskip> If positive, this gives the skip to leave below the heading, else it gives the skip to leave to the right of a run-in heading.

<style> Commands to set the style of the heading.

- * When this is missing the heading is numbered and the corresponding counter is incremented.

<altheading> Gives an alternative heading to use in the table of contents and in the running heads. This should be present when the * form is used.

<heading> The heading of the new section.

A sectioning command is normally defined to `\@startsection` and its first six arguments.

The macro `\secdef` can be used when a sectioning command is defined without using `\@startsection`. It has two arguments:

```
\secdef<unstarcmds><starcmds>
```

<unstarcmds> Used for the normal form of the sectioning command.

<starcmds> Used for the *-form of the sectioning command.

You can use `\secdef` as follows:

```
\def\chapter{... \secdef \CMDA \CMDB }
\def\CMDA [#1]{ ... } % Command to define
% \chapter[...]{...}
\def\CMDB #1{ ... } % Command to define
% \chapter*{...}
```

7.2.2 Mark commands

<code>\chaptermark</code>	Default initializations of <code>\...mark</code> commands. These commands are used in the definition of the page styles (see section 6.4.2) Most of them are already defined by <code>latex.dtx</code> , so they are only shown here.
<code>\sectionmark</code>	
<code>\subsectionmark</code>	
<code>\subsubsectionmark</code>	
<code>\paragraphmark</code>	
<code>\ subparagraphmark</code>	
	630 <code>!article\newcommand*\chaptermark[1]{}%</code>
	631 <code>% \newcommand*\sectionmark[1]{}%</code>
	632 <code>% \newcommand*\subsectionmark[1]{}%</code>
	633 <code>% \newcommand*\subsubsectionmark[1]{}%</code>
	634 <code>% \newcommand*\paragraphmark[1]{}%</code>
	635 <code>% \newcommand*\ subparagraphmark[1]{}%</code>

7.2.3 Define Counters

<code>\c@secnumdepth</code>	The value of the counter <code>secnumdepth</code> gives the depth of the highest-level sectioning command that is to produce section numbers.
	636 <code><article\setcounter{secnumdepth}{3}%</code>
	637 <code><article\setcounter{secnumdepth}{2}%</code>
<code>\c@part</code>	These counters are used for the section numbers. The macro
<code>\c@chapter</code>	<code>\newcounter{<newctr>}[<oldctr>]</code>
<code>\c@section</code>	defines <code><newctr></code> to be a counter, which is reset to zero when counter <code><oldctr></code> is stepped. Counter <code><oldctr></code> must already be defined.
<code>\c@subsection</code>	
<code>\c@subsubsection</code>	
<code>\c@paragraph</code>	
<code>\c@ subparagraph</code>	
	638 <code>\newcounter {part}</code>

```

639 <article>\newcounter {section}
640 {*report | book}
641 \newcounter {chapter}
642 \newcounter {section}[chapter]
643 //report | book)
644 \newcounter {subsection}[section]
645 \newcounter {subsubsection}[subsection]
646 \newcounter {paragraph}[subsubsection]
647 \newcounter { subparagraph}[paragraph]

\the part
\the chapter
\the section
\the subsection
\the subsubsection
\the paragraph
\the subparagraph

```

For any counter *CTR*, `\theCTR` is a macro that defines the printed version of counter *CTR*. It is defined in terms of the following macros:

- `\arabic{COUNTER}` prints the value of *COUNTER* as an arabic numeral.
- `\roman{COUNTER}` prints the value of *COUNTER* as a lowercase roman numeral.
- `\Roman{COUNTER}` prints the value of *COUNTER* as an uppercase roman numeral.
- `\alph{COUNTER}` prints the value of *COUNTER* as a lowercase letter: 1 = a, 2 = b, etc.
- `\Alpha{COUNTER}` prints the value of *COUNTER* as an uppercase letter: 1 = A, 2 = B, etc.

Actually to save space the internal counter representations and the commands operating on those are used.

```

648 \renewcommand \the part {\@Roman\c@part}
649 <article>\renewcommand \the section {\@arabic\c@section}
650 {*report | book}
651 \renewcommand \the chapter {\@arabic\c@chapter}
652 \renewcommand \the subsection {\the chapter.\@arabic\c@section}
653 //report | book)
654 \renewcommand \the subsection {\the section.\@arabic\c@subsection}
655 \renewcommand \the subsubsection {\the subsection.\@arabic\c@subsubsection}
656 \renewcommand \the paragraph {\the subsubsection.\@arabic\c@paragraph}
657 \renewcommand \the subparagraph {\the paragraph.\@arabic\c@subparagraph}

```

`\@chapapp` is initially defined to be ‘`\chaptername`’. The `\appendix` command redefines it to be ‘`\appendixname`’.

```

658 <report | book>\newcommand \@chapapp{\chaptername}

```

7.2.4 Front Matter, Main Matter, and Back Matter

A book contains these three (logical) sections. The switch `\@mainmatter` is true iff we are processing Main Matter. When this switch is false, the `\chapter` command does not print chapter numbers.

Here we define the commands that start these sections.

- | | |
|---------------------------|---|
| <code>\frontmatter</code> | This command starts Roman page numbering and turns off chapter numbering. Since this restarts the page numbering from 1, it should also ensure that a recto page is used. |
| | <pre> 659 {*book} 660 \newcommand\frontmatter{% 661 % \if@openright 662 % \cleardoublepage 663 % \else 664 % \clearpage 665 % \fi 666 % \@mainmatterfalse 667 \pagenumbering{roman}} </pre> |
| <code>\mainmatter</code> | This command clears the page, starts arabic page numbering and turns on chapter numbering. Since this restarts the page numbering from 1, it should also ensure that a recto page is used. |

```

668 \newcommand\mainmatter{%
669 %   \if@openright
670     \cleardoublepage
671 %   \else
672     \clearpage
673 %   \fi
674   \c@mainmattertrue
675   \pagenumbering{arabic}}

```

- \backmatter This clears the page, turns off chapter numbering and leaves page numbering unchanged.

```

676 \newcommand\backmatter{%
677   \if@openright
678     \cleardoublepage
679   \else
680     \clearpage
681   \fi
682   \c@mainmatterfalse}
683 
```

7.2.5 Parts

- \part The command to start a new part of our document.

In the article class the definition of \part is rather simple; we start a new paragraph, add a little white space, suppress the indentation of the first paragraph and make use of \secdef. As in other sectioning commands (cf. \c@startsection in the L^AT_EX 2 _{ε} kernel), we need to check the \c@noskipsec switch and force horizontal mode if it is set.

```

684 <*article>
685 \newcommand\part{%
686   \if@noskipsec \leavevmode \fi
687   \par
688   \addvspace{4ex}%
689   \c@afterindentfalse
690   \secdef\c@part\c@spart}
691 
```

For the report and book classes we things a bit different.

We start a new (righthand) page and use the *plain* pagestyle.

```

692 <*report | book>
693 \newcommand\part{%
694   \if@openright
695     \cleardoublepage
696   \else
697     \clearpage
698   \fi
699   \thispagestyle{plain}%

```

When we are making a two column document, this will be a one column page. We use \c@tempswa to remember to switch back to two columns.

```

700   \if@twocolumn
701     \onecolumn
702     \c@tempswatrue
703   \else
704     \c@tempswafalse
705   \fi

```

We need an empty box to prevent the fil glue from disappearing.

```
706   \null\vfil
```

Here we use \secdef to indicate which commands to use to make the actual heading.

```

707   \secdef\c@part\c@spart}
708 
```

\@part This macro does the actual formatting of the title of the part. Again the macro is differently defined for the article document class than for the document classes report and book.

When *secnumdepth* is larger than -1 for the document class article, we have a numbered part, otherwise it is unnumbered.

```
709 <*article>
710 \def\@part[#1]#2{%
711   \ifnum \c@secnumdepth >\m@ne
712     \refstepcounter{part}%
713     \addcontentsline{toc}{part}{\thepart\hspace{1em}#1}%
714   \else
715     \addcontentsline{toc}{part}{#1}%
716   \fi}
```

We print the title flush left in the article class. Also we prevent breaking between lines and reset the font.

```
717   \parindent \z@ \raggedright
718   \interlinepenalty \OM
719   \normalfont
```

When this is a numbered part we have to print the number and the title. The \nobreak should prevent a page break here.

```
720   \ifnum \c@secnumdepth >\m@ne
721     \Large\bfseries \partname\nobreakspace\thepart
722     \par\nobreak
723   \fi
724   \huge \bfseries #2%
```

Now we empty the mark registers, leave some white space and let \@afterheading take care of suppressing the indentation.

```
725   \markboth{}{}\par}%
726   \nobreak
727   \vskip 3ex
728   \@afterheading}
729 </article>
```

When *secnumdepth* is larger than -2 for the document class report and book, we have a numbered part, otherwise it is unnumbered.

```
730 <*report | book>
731 \def\@part[#1]#2{%
732   \ifnum \c@secnumdepth >-2\relax
733     \refstepcounter{part}%
734     \addcontentsline{toc}{part}{\thepart\hspace{1em}#1}%
735   \else
736     \addcontentsline{toc}{part}{#1}%
737   \fi}
```

We empty the mark registers and center the title on the page in the report and book document classes. Also we prevent breaking between lines and reset the font.

```
738   \markboth{}{}\%
739   {\centering
740   \interlinepenalty \OM
741   \normalfont}
```

When this is a numbered part we have to print the number.

```
742   \ifnum \c@secnumdepth >-2\relax
743     \huge\bfseries \partname\nobreakspace\thepart
744     \par
```

We leave some space before we print the title and leave the finishing up to \endpart.

```
745   \vskip 20\p@
746   \fi
747   \Huge \bfseries #2\par}%
```

```

748      \@endpart}
749 </report | book>

```

- \@spart This macro does the actual formatting of the title of the part when the star form of the user command was used. In this case we *never* print a number. Otherwise the formatting is the same.

The differences between the definition of this macro in the article document class and in the report and book document classes are similar as they were for \@part.

```

750 <*article>
751 \def\@spart#1{%
752   {\parindent \z@ \raggedright
753    \interlinepenalty \OM
754    \normalfont
755    \huge \bfseries #1\par}%
756    \nobreak
757    \vskip 3ex
758    \cafterheading}
759 </article>
760 <*report | book>
761 \def\@spart#1{%
762   {\centering
763    \interlinepenalty \OM
764    \normalfont
765    \Huge \bfseries #1\par}%
766    \caendpart}
767 </report | book>

```

- \@endpart This macro finishes the part page, for both \@part and \@spart.

First we fill the current page.

```

768 <*report | book>
769 \def\@endpart{\vfil\newpage

```

Then, when we are in twosided mode and chapters are supposed to be on right hand sides, we produce a completely blank page.

```

770           \if@twoside
771             \if@openright
772               \null
773               \thispagestyle{empty}%
774               \newpage
775             \fi
776           \fi

```

When this was a two column document we have to switch back to two column mode.

```

777           \if@tempswa
778             \twocolumn
779           \fi}
780 </report | book>

```

7.2.6 Chapters

- \chapter A chapter should always start on a new page therefore we start by calling \clearpage and setting the pagestyle for this page to *plain*.

```

781 <*report | book>
782 \newcommand\chapter{\if@openright\cleardoublepage\else\clearpage\fi
783   \thispagestyle{plain}%

```

Then we prevent floats from appearing at the top of this page because it looks weird to see a floating object above a chapter title.

```

784           \global\@topnum\z@

```

Then we suppress the indentation of the first paragraph by setting the switch `\@afterindent` to `false`. We use `\secdef` to specify the macros to use for actually setting the chapter title.

```
785          \@afterindentfalse
786          \secdef\@chapter\@schapter}
```

- `\@chapter` This macro is called when we have a numbered chapter. When `secnumdepth` is larger than `-1` and, in the book class, `\@mainmatter` is true, we display the chapter number. We also inform the user that a new chapter is about to be typeset by writing a message to the terminal.

```
787 \def\@chapter[#1]{\ifnum \c@secnumdepth >\m@ne
788   \if@mainmatter
789     \refstepcounter{chapter}%
790     \typeout{\@chapapp\space\thechapter.}%
791     \addcontentsline{toc}{chapter}%
792       {\protect\numberline{\thechapter}#1}%
793   \else
794     \addcontentsline{toc}{chapter}{#1}%
795   \fi
796
797 \else
798   \addcontentsline{toc}{chapter}{#1}%
799 \fi
800 }
```

After having written an entry to the table of contents we store the (alternative) title of this chapter with `\chaptermark` and add some white space to the lists of figures and tables.

```
801   \chaptermark{#1}%
802   \addtocontents{lof}{\protect\addvspace{10\p@}}%
803   \addtocontents{lot}{\protect\addvspace{10\p@}}%
```

Then we call upon `\@makechapterhead` to format the actual chapter title. We have to do this in a special way when we are in `twocolumn` mode in order to have the chapter title use the entire `\textwidth`. In one column mode we call `\@afterheading` which takes care of suppressing the indentation.

```
804   \if@twocolumn
805     \atopnewpage[\@makechapterhead{#2}]%
806   \else
807     \@makechapterhead{#2}%
808     \@afterheading
809   \fi}
```

- `\@makechapterhead` The macro above uses `\@makechapterhead{text}` to format the heading of the chapter.

We begin by leaving some white space. Then we open a group in which we have a paragraph indent of `0pt`, and in which we have the text set ragged right. We also reset the font.

```
810 \def\@makechapterhead#1{%
811   \vspace*{50\p@}%
812   {\parindent \z@ \raggedright \normalfont
```

Then we check whether the number of the chapter has to be printed. If so we leave some whitespace between the chapter number and its title.

```
813   \ifnum \c@secnumdepth >\m@ne
814   \book \if@mainmatter
815     \huge\bfseries \@chapapp\space \thechapter
816     \par\nobreak
817     \vskip 20\p@
818 \book \fi
819 \fi
```

Now we set the title in a large bold font. We prevent a pagebreak from occurring in the middle of or after the title. Finally we leave some whitespace before the text begins.

```
820     \interlinepenalty\@M
821     \Huge \bfseries #1\par\nobreak
822     \vskip 40\p@
823 }
```

\@schapter This macro is called when we have an unnumbered chapter. It is much simpler than **\@chapter** because it only needs to typeset the chapter title.

```
824 \def\@schapter#1{\if@twocolumn
825     \atopnewpage[\@makeschapterhead{#1}]%
826     \else
827         \@makeschapterhead{#1}%
828         \@afterheading
829     \fi}
```

\@makeschapterhead The macro above uses **\@makeschapterhead**(*text*) to format the heading of the chapter. It is similar to **\@makechapterhead** except that it never has to print a chapter number.

```
830 \def\@makeschapterhead#1{%
831     \vspace*{50\p@}%
832     {\parindent \z@ \raggedright
833         \normalfont
834         \interlinepenalty\@M
835         \Huge \bfseries #1\par\nobreak
836         \vskip 40\p@
837     }%
838 } /report | book>
```

7.2.7 Lower level headings

These commands all make use of **\@startsection**.

\section This gives a normal heading with white space above and below the heading, the title set in **\Large\bfseries**, and no indentation on the first paragraph.

```
839 \newcommand\section{\@startsection {section}{1}{\z@}%
840             {-3.5ex \oplus -1ex \ominus -.2ex}%
841             {2.3ex \oplus .2ex}%
842             {\normalfont\Large\bfseries}}
```

\subsection This gives a normal heading with white space above and below the heading, the title set in **\large\bfseries**, and no indentation on the first paragraph.

```
843 \newcommand\subsection{\@startsection {subsection}{2}{\z@}%
844             {-3.25ex \oplus -1ex \ominus -.2ex}%
845             {1.5ex \oplus .2ex}%
846             {\normalfont\large\bfseries}}
```

\subsubsection This gives a normal heading with white space above and below the heading, the title set in **\normalsize\bfseries**, and no indentation on the first paragraph.

```
847 \newcommand\subsubsection{\@startsection {subsubsection}{3}{\z@}%
848             {-3.25ex \oplus -1ex \ominus -.2ex}%
849             {1.5ex \oplus .2ex}%
850             {\normalfont\normalsize\bfseries}}
```

\paragraph This gives a run-in heading with white space above and to the right of the heading, the title set in **\normalsize\bfseries**.

```
851 \newcommand\paragraph{\@startsection {paragraph}{4}{\z@}%
852             {3.25ex \oplus 1ex \ominus .2ex}%
853             {-1em}%
854             {\normalfont\normalsize\bfseries}}
```

\subparagraph This gives an indented run-in heading with white space above and to the right of the heading, the title set in \normalsize\bfseries.

```

855 \newcommand\subparagraph{\@startsection{subparagraph}{5}{\parindent}%
856                                     {3.25ex \@plus1ex \@minus .2ex}%
857                                     {-1em}%
858                                     {\normalfont\normalsize\bfseries}}

```

7.3 Lists

7.3.1 General List Parameters

The following commands are used to set the default values for the list environment's parameters. See the L^AT_EX manual for an explanation of the meanings of the parameters. Defaults for the list environment are set as follows. First, \rightmargin, \listparindent and \itemindent are set to 0pt. Then, for a Kth level list, the command \clistK is called, where 'K' denotes 'i', 'ii', ... , 'vi'. (I.e., \clistiii is called for a third-level list.) By convention, \clistK should set \leftmargin to \leftmarginK.

\leftmargin	When we are in two column mode some of the margins are set somewhat smaller.
\leftmargini	859 \if@twocolumn
\leftmarginii	860 \setlength{\leftmargini} {2em}
\leftmarginiii	861 \else
\leftmarginiv	862 \setlength{\leftmargini} {2.5em}
\leftmarginv	863 \fi
\leftmarginvi	Until the whole of the parameter setting in these files is rationalised, we need to set the value of \leftmargin at this outer level.
	864 \leftmargin \leftmargini
	The following three are calculated so that they are larger than the sum of \labelsep and the width of the default labels (which are '(m)', 'vii.' and 'M.').
	865 \setlength{\leftmarginii} {2.2em}
	866 \setlength{\leftmarginiii} {1.87em}
	867 \setlength{\leftmarginiv} {1.7em}
	868 \if@twocolumn
	869 \setlength{\leftmarginv} {.5em}
	870 \setlength{\leftmarginvi} {.5em}
	871 \else
	872 \setlength{\leftmarginv} {1em}
	873 \setlength{\leftmarginvi} {1em}
	874 \fi
\labelsep	\labelsep is the distance between the label and the text of an item; \labelwidth is the width of the label.
\labelwidth	875 \setlength{\labelsep} {.5em}
	876 \setlength{\labelwidth}{\leftmargini}
	877 \addtolength{\labelwidth}{-\labelsep}
\partopsep	When the user leaves a blank line before the environment an extra vertical space of \partopsep is inserted, in addition to \parskip and \topsep.
	878 //article report book
	879 {10pt}\setlength{\partopsep}{2\p0 \oplus 1\p0 \minus 1\p0}
	880 {11pt}\setlength{\partopsep}{3\p0 \oplus 1\p0 \minus 1\p0}
	881 {12pt}\setlength{\partopsep}{3\p0 \oplus 2\p0 \minus 2\p0}
\@beginparpenalty	These penalties are inserted before and after a list or paragraph environment.
\@endparpenalty	They are set to a bonus value to encourage page breaking at these points.
\@itempenalty	This penalty is inserted between list items.
	882 /*article report book
	883 \@beginparpenalty -\@lowpenalty

```

884 \@endparpenalty    -\@lowpenalty
885 \@itempenalty      -\@lowpenalty
886 </article | report | book>

\@listi  \@listi defines the values of \leftmargin, \parsep, \topsep, \itemsep, etc.
\@listI  for the lists that appear on top-level. Its definition is modified by the font-size
          commands (eg within \small the list parameters get “smaller” values).

          For this reason listI is defined to hold a saved copy of listi so that \normalsize
          can switch all parameters back.

887 <*10pt | 11pt | 12pt>
888 \def\@listi{\leftmargin\leftmargini
889 <*10pt>
890           \parsep 4\p@ \oplus2\p@ \ominus\p@
891           \topsep 8\p@ \oplus2\p@ \ominus4\p@
892           \itemsep4\p@ \oplus2\p@ \ominus\p@
893 </10pt>
894 <*11pt>
895           \parsep 4.5\p@ \oplus2\p@ \ominus\p@
896           \topsep 9\p@ \oplus3\p@ \ominus5\p@
897           \itemsep4.5\p@ \oplus2\p@ \ominus\p@
898 </11pt>
899 <*12pt>
900           \parsep 5\p@ \oplus2.5\p@ \ominus\p@
901           \topsep 10\p@ \oplus4\p@ \ominus6\p@
902           \itemsep5\p@ \oplus2.5\p@ \ominus\p@
903 </12pt>
904 \let\@listI\@listi

```

We initialise the parameters although strictly speaking that is not necessary.

```
905 \@listi
```

```

\@listii  Here are the same macros for the higher level lists. Note that they don't have
\@listiii  saved versions and are not modified by the font size commands. In other words
\@listiv  this class assumes that nested lists only appear in \normalsize, i.e. the main
          document size.

\@listvi  906 \def\@listii {\leftmargin\leftmarginii
907           \labelwidth\leftmarginii
908           \advance\labelwidth-\labelsep
909 <*10pt>
910           \topsep    4\p@ \oplus2\p@ \ominus\p@
911           \parsep    2\p@ \oplus\p@ \ominus\p@
912 </10pt>
913 <*11pt>
914           \topsep    4.5\p@ \oplus2\p@ \ominus\p@
915           \parsep    2\p@ \oplus\p@ \ominus\p@
916 </11pt>
917 <*12pt>
918           \topsep    5\p@ \oplus2.5\p@ \ominus\p@
919           \parsep    2.5\p@ \oplus\p@ \ominus\p@
920 </12pt>
921           \itemsep   \parsep}
922 \def\@listiii{\leftmargin\leftmarginiii
923           \labelwidth\leftmarginiii
924           \advance\labelwidth-\labelsep
925 <10pt>        \topsep    2\p@ \oplus\p@\ominus\p@
926 <11pt>        \topsep    2\p@ \oplus\p@\ominus\p@
927 <12pt>        \topsep    2.5\p@\oplus\p@\ominus\p@
928           \parsep    \z@%
929           \partopsep \p@ \oplus\z@ \ominus\p@
930           \itemsep   \topsep}
931 \def\@listiv {\leftmargin\leftmarginiv
932           \labelwidth\leftmarginiv

```

```

933           \advance\labelwidth-\labelsep}
934 \def\@listv {\leftmargin\leftmarginiv
935           \labelwidth\leftmarginiv
936           \advance\labelwidth-\labelsep}
937 \def\@listvi {\leftmargin\leftmarginvi
938           \labelwidth\leftmarginvi
939           \advance\labelwidth-\labelsep}
940 </10pt | 11pt | 12pt>

```

7.3.2 Enumerate

The enumerate environment uses four counters: *enumi*, *enumii*, *enumiii* and *enumiv*, where *enumN* controls the numbering of the Nth level enumeration.

\theenumi	The counters are already defined in <i>latex.dtx</i> , but their representation is changed here.
\theenumii	941 <*article report book>
\theenumiv	942 \renewcommand\theenumi{\@arabic\c@enumi}
	943 \renewcommand\theenumii{\@alph\c@enumii}
	944 \renewcommand\theenumiii{\@roman\c@enumiii}
	945 \renewcommand\theenumiv{\@Alph\c@enumiv}
\labelenumi	The label for each item is generated by the commands
\labelenumii	\labelenumi ... \labelenumiv.
\labelenumiii	946 \newcommand\labelenumi{\theenumi.}
\labelenumiv	947 \newcommand\labelenumii{(\theenumii)}
	948 \newcommand\labelenumiii{(\theenumiii.)}
	949 \newcommand\labelenumiv{(\theenumiv.)}
\p@enumii	The expansion of \p@enumN\theenumN defines the output of a \ref command when referencing an item of the Nth level of an enumerated list.
\p@enumiii	
\p@enumiv	950 \renewcommand\p@enumii{\theenumi}
	951 \renewcommand\p@enumiii{(\theenumi(\theenumii))}
	952 \renewcommand\p@enumiv{\p@enumiii\theenumiii}

7.3.3 Itemize

\labelitemi	Itemization is controlled by four commands: \labelitemi, \labelitemii,
\labelitemii	\labelitemiii, and \labelitemiv, which define the labels of the various itemization levels: the symbols used are bullet, bold en-dash, centered asterisk and centred dot.
\labelitemiii	
\labelitemiv	
	953 \newcommand\labelitemi{\textbullet}
	954 \newcommand\labelitemii{\normalfont\bfseries \textendash}
	955 \newcommand\labelitemiii{\textasteriskcentered}
	956 \newcommand\labelitemiv{\textperiodcentered}

7.3.4 Description

description	The description environment is defined here – while the itemize and enumerate environments are defined in <i>latex.dtx</i> .

```

957 \newenvironment{description}
958           {\list{}{\labelwidth\z@\itemindent-\leftmargin
959                     \let\makelabel\descriptionlabel}}
960           {\endlist}

```

\descriptionlabel	To change the formatting of the label, you must redefine \descriptionlabel.

```

961 \newcommand*\descriptionlabel[1]{\hspace\labelsep
962                               \normalfont\bfseries #1}

```

7.4 Defining new environments

7.4.1 Abstract

abstract When we are producing a separate titlepage we also put the abstract on a page of its own. It will be centred vertically on the page.

Note that this environment is not defined for books.

```
963 % \changes{v1.3m}{1995/10/23}{Added setting of \cs{beginparpenalty} to  
964 %   discourage page break before abstract heading.}  
965 <*article | report>  
966 \if@titlepage  
967   \newenvironment{abstract}{%  
968     \titlepage  
969     \null\vfil  
970     \begin{parpenalty}\@lowpenalty  
971     \begin{center}%  
972       \bfseries \abstractname  
973       \end{parpenalty}\@M  
974     \end{center}}%  
975   {\par\vfil\null\endtitlepage}
```

When we are not making a separate titlepage –the default for the article document class– we have to check if we are in twocolumn mode. In that case the abstract is as a `\section*`, otherwise the quotation environment is used to typeset the abstract.

```
976 \else  
977   \newenvironment{abstract}{%  
978     \if@twocolumn  
979       \section*\{\abstractname\}%  
980     \else  
981       \small  
982       \begin{center}%  
983         \bfseries \abstractname\vspace{- .5em}\vspace{\z@}}%  
984       \end{center}}%  
985       \quotation  
986     \fi  
987   {\if@twocolumn\else\endquotation\fi}  
988 \fi  
989 </article | report>
```

7.4.2 Verse

verse The verse environment is defined by making clever use of the list environment’s parameters. The user types `\\\` to end a line. This is implemented by `\let`’ing `\\\` equal `\@centercr`.

```
990 \newenvironment{verse}  
991   {\let\\\@centercr  
992     \list{}{\itemsep \z@  
993       \itemindent -1.5em%  
994       \listparindent\itemindent  
995       \rightmargin \leftmargin  
996       \advance\leftmargin 1.5em}%  
997     \item\relax  
998   \endlist}
```

7.4.3 Quotation

quotation The quotation environment is also defined by making clever use of the list environment’s parameters. The lines in the environment are set smaller than `\textwidth`. The first line of a paragraph inside this environment is indented.

```
999 \newenvironment{quotation}  
1000   {\list{}{\listparindent 1.5em%
```

```

1001           \itemindent    \listparindent
1002           \rightmargin   \leftmargin
1003           \parsep       \z@ \cplus\p@}%
1004           \item\relax}
1005           {\endlist}

```

7.4.4 Quote

- quote** The quote environment is like the quotation environment except that paragraphs are not indented.

```

1006 \newenvironment{quote}
1007     {\list{}{\rightmargin\leftmargin}%
1008     \item\relax}
1009     {\endlist}

```

7.4.5 Theorem

This document class does not define it's own theorem environments, the defaults, supplied by `latex.dtx` are available.

7.4.6 Titlepage

- titlepage** In the normal environments, the titlepage environment does nothing but start and end a page, and inhibit page numbers. In the report style, it also resets the page number to one, and then sets it back to one at the end. In compatibility mode, it sets the page number to zero. This is incorrect since it results in using the page parameters for a right-hand page but it is the way it was. In two-column style, it still makes a one-column page.

First we do give the definition for compatibility mode.

```

1010 \if@compatibility
1011 \newenvironment{titlepage}
1012     {%
1013 <book>      \cleardoublepage
1014     \if@twocolumn
1015         \restonecoltrue\onecolumn
1016     \else
1017         \restonecolfalse\newpage
1018     \fi
1019     \thispagestyle{empty}%
1020     \setcounter{page}\z@
1021 }
1022 {\if@restonecol\twocolumn \else \newpage \fi
1023 }

```

And here is the one for native L^AT_EX 2_&.

```

1024 \else
1025 \newenvironment{titlepage}
1026     {%
1027 <book>      \cleardoublepage
1028     \if@twocolumn
1029         \restonecoltrue\onecolumn
1030     \else
1031         \restonecolfalse\newpage
1032     \fi
1033     \thispagestyle{empty}%
1034     \setcounter{page}\@ne
1035 }
1036 {\if@restonecol\twocolumn \else \newpage \fi

```

If we are not in two-side mode the first page after the title page should also get page number 1.

```
1037 \if@twoside\else
```

```

1038         \setcounter{page}\@ne
1039     \fi
1040 }
1041 \fi

```

7.4.7 Appendix

`\appendix` The `\appendix` command is not really an environment, it is a macro that makes some changes in the way things are done.

In the article document class the `\appendix` command must do the following:

- reset the section and subsection counters to zero,
- redefine `\thesection` to produce alphabetic appendix numbers. This redefinition is done globally to ensure that it survives even if `\appendix` is issued within an environment such as `multicols`.

```

1042 <*article>
1043 \newcommand\appendix{\par
1044   \setcounter{section}{0}%
1045   \setcounter{subsection}{0}%
1046   \gdef\thesection{@Alph\c@section}%
1047 </article>

```

In the report and book document classes the `\appendix` command must do the following:

- reset the chapter and section counters to zero,
- set `\chapapp` to `\appendixname` (for messages),
- redefine the chapter counter to produce appendix numbers,
- possibly redefine the `\chapter` command if appendix titles and headings are to look different from chapter titles and headings. This redefinition is done globally to ensure that it survives even if `\appendix` is issued within an environment such as `multicols`.

```

1048 <*report | book>
1049 \newcommand\appendix{\par
1050   \setcounter{chapter}{0}%
1051   \setcounter{section}{0}%
1052   \gdef\chapapp{\appendixname}%
1053   \gdef\thechapter{@Alph\c@chapter}%
1054 </report | book>

```

7.5 Setting parameters for existing environments

7.5.1 Array and tabular

`\arraycolsep` The columns in an array environment are separated by $2\arraycolsep$.

```
1055 \setlength\arraycolsep{5\p@}
```

`\tabcolsep` The columns in an tabular environment are separated by $2\tabcolsep$.

```
1056 \setlength\tabcolsep{6\p@}
```

`\arrayrulewidth` The width of rules in the array and tabular environments is given by `\arrayrulewidth`.

```
1057 \setlength\arrayrulewidth{.4\p@}
```

`\doublerulesep` The space between adjacent rules in the array and tabular environments is given by `\doublerulesep`.

```
1058 \setlength\doublerulesep{2\p@}
```

7.5.2 Tabbing

- \tabbingsep This controls the space that the \` command puts in. (See L^AT_EX manual for an explanation.)
1059 \setlength\tabbingsep{\labelsep}

7.5.3 Minipage

- \@minipagerestore The macro \@minipagerestore is called upon entry to a minipage environment to set up things that are to be handled differently inside a minipage environment. In the current styles, it does nothing.

- \@mpfootins Minipages have their own footnotes; \skip\@mpfootins plays same rôle for footnotes in a minipage as \skip\footins does for ordinary footnotes.
1060 \skip\@mpfootins = \skip\footins

7.5.4 Framed boxes

- \fboxsep The space left by \fbox and \framebox between the box and the text in it.
\fboxrule The width of the rules in the box made by \fbox and \framebox.
1061 \setlength\fboxsep{3\p@}
1062 \setlength\fboxrule{.4\p@}

7.5.5 Equation and eqnarray

- \theequation When within chapters, the equation counter will be reset at the beginning of a new chapter and the equation number will be prefixed by the chapter number.
This code must follow the \chapter definition or, more exactly, the definition of the chapter counter.
1063 <article>\renewcommand \theequation {\@arabic\c@equation}
1064 <*report | book>
1065 \@addtoreset {equation}{chapter}
1066 \renewcommand\theequation
1067 {\ifnum \c@chapter>\z@ \thechapter.\fi \@arabic\c@equation}
1068 </report | book>

- \jot \jot is the extra space added between lines of an eqnarray environment. The default value is used.
1069 % \setlength\jot{3pt}

- \@eqnnum The macro \@eqnnum defines how equation numbers are to appear in equations. Again the default is used.
1070 % \def\@eqnnum{(\theequation)}

7.6 Floating objects

The file `latex.dtx` only defines a number of tools with which floating objects can be defined. This is done in the document class. It needs to define the following macros for each floating object of type TYPE (e.g., TYPE = figure).

\fps@TYPE The default placement specifier for floats of type TYPE.

\ftype@TYPE The type number for floats of type TYPE. Each TYPE has associated a unique positive TYPE number, which is a power of two. E.g., figures might have type number 1, tables type number 2, programs type number 4, etc.

\ext@TYPE The file extension indicating the file on which the contents list for float type TYPE is stored. For example, \ext@figure = ‘lof’.

`\fnum@TYPE` A macro to generate the figure number for a caption. For example, `\fnum@TYPE == 'Figure \thefigure'`.

`\@makecaption<num><text>` A macro to make a caption, with `<num>` the value produced by `\fnum@...` and `<text>` the text of the caption. It can assume it's in a `\parbox` of the appropriate width. This will be used for *all* floating objects.

The actual environment that implements a floating object such as a figure is defined using the macros `\@float` and `\end@float`, which are defined in `latex.dtx`.

An environment that implements a single column floating object is started with `\@float{TYPE}[<placement>]` of type TYPE with `<placement>` as the placement specifier. The default value of `<PLACEMENT>` is defined by `\fps@TYPE`.

The environment is ended by `\end@float`. E.g., `\figure == \@float{figure}`, `\endfigure == \end@float`.

7.6.1 Figure

Here is the implementation of the figure environment.

`\c@figure` First we have to allocate a counter to number the figures.

In the report and book document classes figures within chapters are numbered per chapter.

```
1071 <*article>
1072 \newcounter{figure}
1073 \renewcommand{\thefigure}{\@arabic\c@figure}
1074 </article>
1075 <*report | book>
1076 \newcounter{figure}[chapter]
1077 \renewcommand{\thefigure}{\ifnum\c@chapter>\z@\thechapter.\fi\@arabic\c@figure}
1078 </report | book>
```

`\fps@figure` Here are the parameters for the floating objects of type ‘figure’.

```
\ftype@figure 1080 \def\fps@figure{tbp}
\ext@figure 1081 \def\ftype@figure{1}
\num@figure 1082 \def\ext@figure{lof}
1083 \def\fnum@figure{\figurename\nobreakspace\thefigure}
```

`\figure` And the definition of the actual environment. The form with the * is used for double column figures.

```
1084 \newenvironment{figure}
1085   {\@float{figure}}
1086   {\end@float}
1087 \newenvironment{figure*}
1088   {\@dblfloat{figure}}
1089   {\end@dblfloat}
```

7.6.2 Table

Here is the implementation of the table environment. It is very much the same as the figure environment.

`\c@table` First we have to allocate a counter to number the tables.

In the report and book document classes tables within chapters are numbered per chapter.

```
1090 <*article>
1091 \newcounter{table}
1092 \renewcommand{\thetable}{\@arabic\c@table}
1093 </article>
1094 <*report | book>
```

```

1095 \newcounter{table}[chapter]
1096 \renewcommand \thetable
1097   {\ifnum \c@chapter>\z@ \thechapter.\fi \arabic{c@table}}
1098 \report | book>

\fps@table Here are the parameters for the floating objects of type ‘table’.
\ftype@table 1099 \def\fps@table{tbp}
\ext@table 1100 \def\ftype@table{2}
\num@table 1101 \def\ext@table{lot}
1102 \def\fnum@table{\tablename\nobreakspace\thetable}






```

7.6.3 Captions

\@makecaption The \caption command calls \@makecaption to format the caption of floating objects. It gets two arguments, *number*, the number of the floating object and *text*, the text of the caption. Usually *number* contains a string such as ‘Figure 3.2’. The macro can assume it is called inside a \parbox of right width, with \normalsize.

\abovecaptionskip \belowcaptionskip These lengths contain the amount of white space to leave above and below the caption.

```

1109 \newlength\abovecaptionskip
1110 \newlength\belowcaptionskip
1111 \setlength\abovecaptionskip{10\p@}
1112 \setlength\belowcaptionskip{0\p@}

```

The definition of this macro is \long in order to allow more than one paragraph in a caption.

```

1113 \long\def\@makecaption#1#2{%
1114   \vskip\abovecaptionskip

```

We want to see if the caption fits on one line on the page, therefore we first typeset it in a temporary box.

```
1115   \sbox\@tempboxa{#1: #2}%

```

We can then measure its width. If that is larger than the current \hsize we typeset the caption as an ordinary paragraph.

```

1116   \ifdim \wd\@tempboxa >\hsize
1117     #1: #2\par

```

If the caption fits, we center it. Because this uses an \hbox directly in vertical mode, it does not execute the \everypar tokens; the only thing that could be needed here is resetting the ‘minipage flag’ so we do this explicitly.

```

1118   \else
1119     \global \minipagetrue
1120     \hb@xt@\hsize{\hfil\box\@tempboxa\hfil}%
1121   \fi
1122   \vskip\belowcaptionskip

```

7.7 Font changing

Here we supply the declarative font changing commands that were common in L^AT_EX version 2.09 and earlier. These commands work in text mode *and* in math mode. They are provided for compatibility, but one should start using the `\text...` and `\math...` commands instead. These commands are defined using `\DeclareTextFontCommand`, a command with three arguments: the user command to be defined; L^AT_EX commands to execute in text mode and L^AT_EX commands to execute in math mode.

- `\rm` The commands to change the family. When in compatibility mode we select the ‘default’ font first, to get L^AT_EX2.09 behaviour.
- `\sf` 1123 `\DeclareOldFontCommand{\rm}{\normalfont\rmfamily}{\mathrm}`
1124 `\DeclareOldFontCommand{\sf}{\normalfont\sffamily}{\mathsf}`
1125 `\DeclareOldFontCommand{\tt}{\normalfont\ttfamily}{\mathtt}`
- `\bf` The command to change to the bold series. One should use `\mdseries` to explicitly switch back to medium series.
1126 `\DeclareOldFontCommand{\bf}{\normalfont\bfseries}{\mathbf}`
- `\sl` And the commands to change the shape of the font. The slanted and small caps shapes are not available by default as math alphabets, so those changes do nothing in math mode. However, we do warn the user that the selection will not have any effect. One should use `\upshape` to explicitly change back to the upright shape.
1127 `\DeclareOldFontCommand{\it}{\normalfont\itshape}{\mathit}`
1128 `\DeclareOldFontCommand{\sl}{\normalfont\slshape}{\@nomath\sl}`
1129 `\DeclareOldFontCommand{\sc}{\normalfont\scshape}{\@nomath\sc}`
- `\cal` The commands `\cal` and `\mit` should only be used in math mode, outside math mode they have no effect. Currently the New Font Selection Scheme defines these commands to generate warning messages. Therefore we have to define them ‘by hand’.
1130 `\DeclareRobustCommand*\cal{\@fontswitch\relax\mathcal}`
1131 `\DeclareRobustCommand*\mit{\@fontswitch\relax\mathnormal}`

8 Cross Referencing

8.1 Table of Contents, etc.

A `\section` command writes a `\contentsline{section}{\langle title \rangle}{\langle page \rangle}` command on the `.toc` file, where `\langle title \rangle` contains the contents of the entry and `\langle page \rangle` is the page number. If sections are being numbered, then `\langle title \rangle` will be of the form `\numberline{\langle num \rangle}{\langle heading \rangle}` where `\langle num \rangle` is the number produced by `\thesection`. Other sectioning commands work similarly.

A `\caption` command in a ‘figure’ environment writes
`\contentsline{figure}{\numberline{\langle num \rangle}{\langle caption \rangle}}{\langle page \rangle}` on the `.lof` file, where `\langle num \rangle` is the number produced by `\thefigure` and `\langle caption \rangle` is the figure caption. It works similarly for a ‘table’ environment.

The command `\contentsline{\langle name \rangle}` expands to `\l@{\langle name \rangle}`. So, to specify the table of contents, we must define `\l@chapter`, `\l@section`, `\l@subsection`, ... ; to specify the list of figures, we must define `\l@figure`; and so on. Most of these can be defined with the `\@dottedtocline` command, which works as follows.

```
\@dottedtocline{\langle level \rangle}{\langle indent \rangle}{\langle numwidth \rangle}{\langle title \rangle}{\langle page \rangle}
```

`\langle level \rangle` An entry is produced only if `\langle level \rangle <=` value of the `tocdepth` counter.
Note, `\chapter` is level 0, `\section` is level 1, etc.

`\langle indent \rangle` The indentation from the outer left margin of the start of the contents line.

`<numwidth>` The width of a box in which the section number is to go, if `<title>` includes a `\numberline` command.

`\@pnumwidth` This command uses the following three parameters, which are set with a `\newcommand` (so em's can be used to make them depend upon the font).
`\@tocrmarg`
`\@dotsep` `\@pnumwidth` The width of a box in which the page number is put.

`\@tocrmarg` The right margin for multiple line entries. One wants `\@tocrmarg ≥ \@pnumwidth`

`\@dotsep` Separation between dots, in mu units. Should be defined as a number like 2 or 1.7

```
1132 \newcommand{\@pnumwidth}{1.55em}
1133 \newcommand{\@tocrmarg}{2.55em}
1134 \newcommand{\@dotsep}{4.5}
1135 {article}\setcounter{tocdepth}{3}
1136 {!article}\setcounter{tocdepth}{2}
```

8.1.1 Table of Contents

`\tableofcontents` This macro is used to request that L^AT_EX produces a table of contents. In the report and book document classes the tables of contents, figures etc. are always set in single-column style.

```
1137 \newcommand{\tableofcontents}{%
1138 {*report | book}
1139     \if@twocolumn
1140         \restonocoltrue\onecolumn
1141     \else
1142         \restonocolfalse
1143     \fi}
```

The title is set using the `\chapter*` command, making sure that the running head—if one is required—contains the right information.

```
1144     \chapter*{\contentsname}
1145 {/report | book}
1146 {article}     \section*{\contentsname}
1147         \omkboth{%
1148             \MakeUppercase{\contentsname}\{\MakeUppercase{\contentsname}\}}%
```

The the actual table of contents is made by calling `\@starttoc{toc}`. After that we restore twocolumn mode if necessary.

```
1149     \@starttoc{toc}%
1150 {!article}     \if@restonocol\twocolumn\fi
1151 }
```

`\l@part` Each sectioning command needs an additional macro to format its entry in the table of contents, as described above. The macro for the entry for parts is defined in a special way.

First we make sure that if a pagebreak should occur, it occurs *before* this entry. Also a little whitespace is added and a group begun to keep changes local.

```
1152 \newcommand*\l@part[2]{%
1153     \ifnum \c@tocdepth >-2\relax
1154 {article}     \addpenalty\@secpenalty
1155 {!article}     \addpenalty{-\@highpenalty}%
1156     \addvspace{2.25em \oplus \p@}}
```

The macro `\numberline` requires that the width of the box that holds the part number is stored in L^AT_EX's scratch register `\@tempdima`. Therefore we initialize it there even though we do not use `\numberline` internally—the value used is quite large so that something like `\numberline{VIII}` would still work.

```
1157     \setlength{\@tempdima}{3em}%
1158     \begingroup
```

We set `\parindent` to 0pt and use `\rightskip` to leave enough room for the pagenumbers.¹ To prevent overfull box messages the `\parfillskip` is set to a negative value.

```
1159      \parindent \z@ \rightskip \c@pnumwidth
1160      \parfillskip -\c@pnumwidth
```

Now we can set the entry, in a large bold font. We make sure to leave vertical mode, set the part title and add the pagenumber, set flush right.

```
1161      {\leavevmode
1162      \large \bfseries #1\hfil \hb@xt@\c@pnumwidth{\hss #2}\par}
```

Prevent a pagebreak immediately after this entry, but use `\everypar` to reset the `\if@nobreak` switch. Finally we close the group.

```
1163      \nobreak
1164 <article>      \if@compatibility
1165          \global\c@nobreaktrue
1166          \everypar{\global\c@nobreakfalse\everypar{}}
1167 </article>      \fi
1168      \endgroup
1169  \fi}
```

`\l@chapter` This macro formats the entries in the table of contents for chapters. It is very similar to `\l@part`

First we make sure that if a pagebreak should occur, it occurs *before* this entry. Also a little whitespace is added and a group begun to keep changes local.

```
1170 <*report | book>
1171 \newcommand*\l@chapter[2]{%
1172   \ifnum \c@tocdepth >\m@ne
1173     \addpenalty{-\highpenalty}%
1174   \vskip 1.0em \oplus \p@
```

The macro `\numberline` requires that the width of the box that holds the part number is stored in L^AT_EX's scratch register `\c@tempdima`. Therefore we initialize it there even though we do not use `\numberline` internally (the position as well as the values seems questionable but can't be changed without producing compatibility problems). We begin a group, and change some of the paragraph parameters (see also the remark at `\l@part` regarding `\rightskip`).

```
1175      \setlength\c@tempdima{1.5em}%
1176      \begingroup
1177      \parindent \z@ \rightskip \c@pnumwidth
1178      \parfillskip -\c@pnumwidth
```

Then we leave vertical mode and switch to a bold font.

```
1179      \leavevmode \bfseries
```

Because we do not use `\numberline` here, we have do some fine tuning 'by hand', before we can set the entry. We discourage but not disallow a pagebreak immediately after a chapter entry.

```
1180      \advance\leftskip\c@tempdima
1181      \hskip -\leftskip
1182      #1\nobreak\hfil \nobreak\hb@xt@\c@pnumwidth{\hss #2}\par
1183      \penalty\highpenalty
1184      \endgroup
1185  \fi}
1186 </report | book>
```

`\l@section` In the article document class the entry in the table of contents for sections looks much like the chapter entries for the report and book document classes.

¹We should really set `\rightskip` to `\c@tocrmarg` instead of `\c@pnumwidth` (no version of L^AT_EX ever did this), otherwise the `\rightskip` is too small. Unfortunately this can't be changed in L^AT_EX 2_ε as we don't want to create different versions of L^AT_EX 2_ε which produce different typeset output unless this is absolutely necessary; instead we suspend it for L^AT_EX3.

First we make sure that if a pagebreak should occur, it occurs *before* this entry. Also a little whitespace is added and a group begun to keep changes local.

```
1187 <*article>
1188 \newcommand*\l@section[2]{%
1189   \ifnum \c@tocdepth >\z@
1190     \addpenalty\@secpenalty
1191     \addvspace{1.0em \@plus\p@}%

```

The macro `\numberline` requires that the width of the box that holds the part number is stored in L^AT_EX's scratch register `\@tempdima`. Therefore we put it there. We begin a group, and change some of the paragraph parameters (see also the remark at `\l@part` regarding `\rightskip`).

```
1192   \setlength\@tempdima{1.5em}%
1193   \begingroup
1194     \parindent \z@ \rightskip \pnumwidth
1195     \parfillskip -\pnumwidth

```

Then we leave vertical mode and switch to a bold font.

```
1196   \leavevmode \bfseries

```

Because we do not use `\numberline` here, we have do some fine tuning 'by hand', before we can set the entry. We discourage but not disallow a pagebreak immediately after a chapter entry.

```
1197   \advance\leftskip\@tempdima
1198   \hskip -\leftskip
1199   #1\nobreak\hfil \nobreak\hb@xt@{\pnumwidth}{\hss #2}\par
1200   \endgroup
1201   \fi}
1202 </article>

```

In the report and book document classes the definition for `\l@section` is much simpler.

```
1203 <*report | book>
1204 \newcommand*\l@section{@dottedtocline{1}{1.5em}{2.3em}}
1205 </report | book>

```

`\l@subsection` All lower level entries are defined using the macro `\@dottedtocline` (see above).

```
\l@subsubsection
1206 <*article>
1207 \newcommand*\l@subsection{@dottedtocline{2}{1.5em}{2.3em}}
1208 \newcommand*\l@subsubsection{@dottedtocline{3}{3.8em}{3.2em}}
1209 \newcommand*\l@paragraph{@dottedtocline{4}{7.0em}{4.1em}}
1210 \newcommand*\l@subparagraph{@dottedtocline{5}{10em}{5em}}
1211 </article>
1212 <*report | book>
1213 \newcommand*\l@subsection{@dottedtocline{2}{3.8em}{3.2em}}
1214 \newcommand*\l@subsubsection{@dottedtocline{3}{7.0em}{4.1em}}
1215 \newcommand*\l@paragraph{@dottedtocline{4}{10em}{5em}}
1216 \newcommand*\l@subparagraph{@dottedtocline{5}{12em}{6em}}
1217 </report | book>

```

8.1.2 List of figures

`\listoffigures` This macro is used to request that L^AT_EX produces a list of figures. It is very similar to `\tableofcontents`.

```
1218 \newcommand\listoffigures{%
1219 <*report | book>
1220   \if@twocolumn
1221     \restonecoltrue\onecolumn
1222   \else
1223     \restonecolfalse
1224   \fi
1225   \chapter*{\listfigurename}%
1226 </report | book>

```

```

1227 <article>      \section*{\listfigurename}%
1228     \@mkboth{\MakeUppercase\listfigurename}%
1229     {\MakeUppercase\listfigurename}%
1230     \@starttoc{lof}%
1231 <report | book>   \if@restonecol\twocolumn\fi
1232 }

```

\l@figure This macro produces an entry in the list of figures.

```

1233 \newcommand*\l@figure{\@dottedtocline{1}{1.5em}{2.3em}}

```

8.1.3 List of tables

\listoftables This macro is used to request that L^AT_EX produces a list of tables. It is very similar to \tableofcontents.

```

1234 \newcommand\listoftables{%
1235 <*report | book>
1236     \if@twocolumn
1237     \o@restonecoltrue\onecolumn
1238     \else
1239     \o@restonecolfalse
1240     \fi
1241     \chapter*{\listtablename}%
1242 </report | book>
1243 <article>      \section*{\listtablename}%
1244     \@mkboth{%
1245         \MakeUppercase\listtablename}%
1246         {\MakeUppercase\listtablename}%
1247     \@starttoc{lot}%
1248 <report | book>   \if@restonecol\twocolumn\fi
1249 }

```

\l@table This macro produces an entry in the list of tables.

```

1250 \let\l@table\l@figure

```

8.2 Bibliography

\bibindent The “open” bibliography format uses an indentation of \bibindent.

```

1251 \newdimen\bibindent
1252 \setlength\bibindent{1.5em}

```

thebibliography The ‘thebibliography’ environment executes the following commands:

```

\renewcommand{\newblock}{\hskip.11em \oplus.33em \minus.07em}
— Defines the “closed” format, where the blocks (major units of information) of
an entry run together.

```

\sloppy — Used because it’s rather hard to do line breaks in bibliographies,
\sfcod{‘.=1000\relax — Causes a ‘.’ (period) not to produce an end-of-sentence space.

The implementation of this environment is based on the generic list environment. It uses the *enumiv* counter internally to generate the labels of the list.

When an empty ‘thebibliography’ environment is found, a warning is issued.

```

1253 \newenvironment{thebibliography}[1]
1254 <*article>
1255     {\section*{\refname}%

```

The \o@mkboth was moved out of the heading argument since at least in report and book (twocolumn option) there are definitions for \chapter which would swallow it otherwise.

```

1256     \o@mkboth{\MakeUppercase\refname}{\MakeUppercase\refname}%
1257 </article>
1258 <!*article>

```

```

1259      {\chapter*{\bibname}%
1260          \omkboth{\MakeUppercase\bibname}{\MakeUppercase\bibname}%
1261 〈/!article〉
1262      \list{\@biblabel{\@arabic\c@enumiv}}%
1263          {\settowidth\labelwidth{\@biblabel{#1}}%
1264              \leftmargin\labelwidth
1265              \advance\leftmargin\labelsep
1266              \openbib@code
1267              \usecounter{enumiv}%
1268              \let\p@enumiv\empty
1269              \renewcommand\theenumiv{\@arabic\c@enumiv}%
1270      \sloppy

```

This is setting the normal (non-infinite) value of `\clubpenalty` for the whole of this environment, so we must reset its stored value also. (Why is there a % after the second 4000 below?)

```

1271      \clubpenalty4000
1272      \clubpenalty \clubpenalty
1273      \widowpenalty4000%
1274      \sfcode‘.\. @m}
1275      {\def\@noitemerr
1276          {\@latex@warning{Empty ‘thebibliography’ environment}}%
1277      \endlist}

```

\newblock The default definition for `\newblock` is to produce a small space.

```
1278 \newcommand\newblock{\hspace{.11em}\hspace{.33em}\hspace{-.07em}}
```

\openbib@code The default definition for `\openbib@code` is to do nothing. It will be changed by the `openbib` option.

```
1279 \let\openbib@code\empty
```

\@biblabel The label for a `\bibitem[...]` command is produced by this macro. The default from `latex.dtx` is used.

```
1280 % \renewcommand*{\@biblabel}[1]{[#1]\hfill}
```

\@cite The output of the `\cite` command is produced by this macro. The default from `latex.dtx` is used.

```
1281 % \renewcommand*{\@cite}[1]{[#1]}
```

8.3 The index

theindex The environment ‘`theindex`’ can be used for indices. It makes an index with two columns, with each entry a separate paragraph. At the user level the commands `\item`, `\subitem` and `\subsubitem` are used to produce index entries of various levels. When a new letter of the alphabet is encountered an amount of `\indexspace` white space can be added.

```

1282 \newenvironment{theindex}
1283         {\if@twocolumn
1284             \restonecolfalse
1285         \else
1286             \restonecoltrue
1287         \fi
1288 〈article〉
1289 〈!article〉
1290         \twocolumn[\section*{\indexname}]%
1291         \twocolumn[\makeschapterhead{\indexname}]%
1292         \omkboth{\MakeUppercase\indexname}%
1293         {\MakeUppercase\indexname}%
1294         \thispagestyle{plain}\parindent\z@

```

Parameter changes to `\columnseprule` and `\columnsep` have to be done after `\twocolumn` has acted. Otherwise they can affect the last page before the index.

```
1293         \parskip\z@\relax .3\p@\relax
```

```

1294           \columnseprule \z@  

1295           \columnsep 35\p@  

1296           \let\item\@idxitem  

When the document continues after the index and it was a one column document  

we have to switch back to one column after the index.  

1297           {\if@restonecol\onecolumn\else\clearpage\fi}  

  

\@idxitem These macros are used to format the entries in the index.  

\subitem 1298 \newcommand{\@idxitem}{\par\hangindent 40\p@}  

\subsubitem 1299 \newcommand{\subitem}{\@idxitem \hspace*{20\p@}}  

1300 \newcommand{\subsubitem}{\@idxitem \hspace*{30\p@}}  

  

\indexspace The amount of white space that is inserted between ‘letter blocks’ in the index.  

1301 \newcommand{\indexspace}{\par \vskip 10\p@ \oplus5\p@ \ominus3\p@ \relax}

```

8.4 Footnotes

\footnoterule Usually, footnotes are separated from the main body of the text by a small rule. This rule is drawn by the macro `\footnoterule`. We have to make sure that the rule takes no vertical space (see `plain.tex`) so we compensate for the natural height of the rule of 0.4pt by adding the right amount of vertical skip.

To prevent the rule from colliding with the footnote we first add a little negative vertical skip, then we put the rule and make sure we end up at the same point where we began this operation.

```

1302 \renewcommand{\footnoterule}{%  

1303   \kern-3\p@  

1304   \hrule\@width.4\columnwidth  

1305   \kern2.6\p@}

```

\c@footnote Footnotes are numbered within chapters in the report and book document styles.
1306 {!article}\@addtoreset{footnote}{chapter}

\@makefntext The footnote mechanism of L^AT_EX calls the macro `\@makefntext` to produce the actual footnote. The macro gets the text of the footnote as its argument and should use `\@thefnmark` as the mark of the footnote. The macro `\@makefntext` is called when effectively inside a `\parbox` of width `\columnwidth` (i.e., with `\hsize = \columnwidth`).

An example of what can be achieved is given by the following piece of T_EX code.

```

\newcommand{\@makefntext}[1]{%  

  \@setpar{\@par  

    \tempdima = \hsize  

    \advance\tempdima-10pt  

    \parshape \one 10pt \tempdima}%  

  \par  

  \parindent 1em\noindent  

  \hbox to \z@{\hss\@makefnmark}#1}

```

The effect of this definition is that all lines of the footnote are indented by 10pt, while the first line of a new paragraph is indented by 1em. To change these dimensions, just substitute the desired value for ‘10pt’ (in both places) or ‘1em’. The mark is flushright against the footnote.

In these document classes we use a simpler macro, in which the footnote text is set like an ordinary text paragraph, with no indentation except on the first line of a paragraph, and the first line of the footnote. Thus, all the macro must do is set `\parindent` to the appropriate value for succeeding paragraphs and put the proper indentation before the mark.

```

1307 \newcommand{\makefnmark}[1]{%
1308     \parindent 1em%
1309     \noindent
1310     \hbox{\scriptsize\hss\@makefnmark}#1}
1311 %\renewcommand{\makefnmark}{\hbox{\textsuperscript{\normalfont\@thefnmark}}}
1312 %

```

\@makefnmark The footnote markers that are printed in the text to point to the footnotes should be produced by the macro \@makefnmark. We use the default definition for it.

9 Initialization

9.1 Words

This document class is for documents prepared in the English language. To prepare a version for another language, various English words must be replaced. All the English words that require replacement are defined below in command names. These commands may be redefined in any class or package that is customising L^AT_EX for use with non-English languages.

```

\contentsname
\listfigurename 1313 \newcommand{\contentsname}{Contents}
\listtablename 1314 \newcommand{\listfigurename}{List of Figures}
               1315 \newcommand{\listtablename}{List of Tables}

\refname
\bibname 1316 <article> \newcommand{\refname}{References}
\indexname 1317 <report | book> \newcommand{\bibname}{Bibliography}
            1318 \newcommand{\indexname}{Index}

\figurename
\tablename 1319 \newcommand{\figurename}{Figure}
            1320 \newcommand{\tablename}{Table}

\partname
\chaptername 1321 \newcommand{\partname}{Part}
\appendixname 1322 <report | book> \newcommand{\chaptername}{Chapter}
\abstractname 1323 \newcommand{\appendixname}{Appendix}
            1324 <!book> \newcommand{\abstractname}{Abstract}

```

9.2 Date

\today This macro uses the T_EX primitives \month, \day and \year to provide the date of the L^AT_EX-run.

At \begin{document} this definition will be optimised so that the names of all the ‘wrong’ months are not stored. This optimisation is not done here as that would ‘freeze’ \today in any special purpose format made by loading the class file into the format file.

```

1325 \def\today{\ifcase\month\or
1326   January\or February\or March\or April\or May\or June\or
1327   July\or August\or September\or October\or November\or December\fi
1328   \space\number\day, \number\year}

```

9.3 Two column mode

\columnsep This gives the distance between two columns in two column mode.

```
1329 \setlength{\columnsep}{10\p@}
```

\columnseprule This gives the width of the rule between two columns in two column mode. We have no visible rule.

```
1330 \setlength\columnseprule{0\p@}
```

9.4 The page style

We have *plain* pages in the document classes article and report unless the user specified otherwise. In the ‘book’ document class we use the page style *headings* by default. We use arabic pagenumbers.

```
1331 {!book} \pagestyle{plain}
1332 {book} \pagestyle{headings}
1333 \pagenumbering{arabic}
```

9.5 Single or double sided printing

When the *twoside* option wasn’t specified, we don’t try to make each page as long as all the others.

```
1334 \if@twoside
1335 \else
1336   \raggedbottom
1337 \fi
```

When the *twocolumn* option was specified we call *\twocolumn* to activate this mode. We try to make each column as long as the others, but call *sloppy* to make our life easier.

```
1338 \if@twocolumn
1339   \twocolumn
1340   \sloppy
1341   \flushbottom
```

Normally we call *\onecolumn* to initiate typesetting in one column.

```
1342 \else
1343   \onecolumn
1344 \fi
1345 {/article | report | book}
```

Index

Numbers written in italic refer to the page where the corresponding entry is described; numbers underlined refer to the code line of the definition; numbers in roman refer to the code lines where the entry is used.

Symbols		
\@date	542,	\@fontswitch 1130, 1131
\@Roman	648	560, 570, 604, 625 \@fpbot
\@afterheading		440 \@fpsep
. 728, 758, 808, 828		440 \@fptop
\@afterindentfalse	689, 785	440 \@highpenalty . 224,
\@author	541,	1155, 1173, 1183 \@idxitem ... 1296, 1298
557, 569, 603, 622		\@dotsep 1132 \@itempenalty 882
\@beginparpenalty	882, 970	1204, \@dottedtocline 1204,
		1207, 1208, \@endparpenalty 882, 973
\@biblabel		1209, 1210, \@endpart . 748, 766, 768
.. 1262, 1263, 1280		1213, 1214, \@listI 108, 887
\@chapapp . 496, 525,		1215, 1216, 1233 \@listii 906
658, 790, 815, 1052		\@endpart . 748, 766, 768 \@listiii 906
\@chapter	786, 787	\@eqnnum 1070 \@listiv 906
\@cite	1281	\@evenfoot 471, 473, 532 \@listv 906
\@clubpenalty	1272	\@evenhead 471, 474, 533 \@listvi 906
		\@fnssymbol 580

\@lowpenalty .. 224,
883, 884, 885, 970
\@mainmatterfalse ..
..... 666, 682
\@mainmattertrue 8, 674
\@makecaption 1109
\@makechapterhead ..
.... 805, 807, 810
\@makefnmark ..
.... 581, 1310, 1311
\@makefntext . 582, 1307
\@makeschapterhead ..
825, 827, 830, 1289
\@maketitle ... 587,
589, 594, 601, 611
\@medpenalty 224
\@minipagefalse .. 1119
\@minipagerestore 1060
\@mparswitchfalse . 41
\@mparswitchtrue .. 43
\@mpfootins .. 1060
\@nobreakfalse ... 1166
\@nobreaktrue ... 1165
\@noitemerr ... 1275
\@normalsize 87
\@oddfoot ..
.... 471, 473, 509, 532
\@oddhead ..
.... 471, 475, 510, 534
\@openbib@code ...
... 66, 1266, 1279
\@openrightfalse .. 56
\@openrighttrue . 53, 55
\@part ... 690, 707, 709
\@pnumwidth ... 1132,
1159, 1160,
1162, 1177,
1178, 1182,
1194, 1195, 1199
\@ptsize ... 1, 34,
36, 38, 39, 84, 85
\@restonecolfalse ..
.... 1017,
1031, 1142,
1223, 1239, 1284
\@restonecoltrue ..
.... 1015,
1029, 1140,
1221, 1237, 1286
\@roman 944
\@schapter ... 786, 824
\@secpenalty 1154, 1190
\@setfontsize
90, 96, 102, 112,
122, 132, 145,
155, 165, 178,
179, 180, 181,
182, 183, 184,
187, 188, 189,
190, 191, 192,
193, 196, 197,
198, 199, 200, 201

\@settopoint ... 283,
371, 372, 377, 392
\@spart ... 690, 707, 750
\@startsection ... 839,
843, 847, 851, 855
\@starttoc ...
.... 1149, 1230, 1247
\@textsuperscript ..
.... 581, 584, 1311
\@thanks ...
.... 562, 568, 596, 602
\@thefnmark ..
.... 581, 584, 1312
\@title ... 540,
552, 571, 605, 617
\@titlepagefalse .. 5, 50
\@titlepagetrue .. 6, 48
\@tocrmarg ... 1132
\@topnewpage ... 805, 825
\@topnum ... 593, 784
\@twocolumnfalse .. 59
\@twocolumntrue ... 61
\@twosidefalse ... 41
\@twosidetrue ... 43
\@width ... 1304

A

\abovecaptionskip ..
.... 1109, 1114
\abovedisplayshortskip ..
.... 92, 98,
104, 114, 124,
134, 147, 157, 167
\abovedisplayskip ..
.... 91, 97,
103, 107, 113,
123, 133, 141,
146, 156, 166, 174
abstract (environment) ... 963
\abstractname ...
972, 979, 983, 1321
\addcontentsline ...
.... 713, 715, 734,
736, 791, 795, 799
\addtocontents 802, 803
\and ... 575, 609
\appendix ... 1042
\appendixname 1052, 1321
\arraycolsep ... 1055
\arrayrulewidth ... 1057
\AtEndOfPackage ... 65
\author ... 540, 573, 607

B

\backmatter ... 676
\baselineskip ...
.... 286, 287,
288, 289, 294, 296
\baselinestretch ... 207

\belowcaptionskip ..
.... 1109, 1122
\belowdisplayshortskip ..
.... 93, 99,
105, 115, 125,
135, 148, 158, 168
\belowdisplayskip ..
.... 107, 141, 174
\bf 1126
\bibindent 67, 68, 1251
\bibname 1259, 1260, 1316
\bigskipamount ... 219
\bottomfraction ... 405
\brokenpenalty ... 234

C

\c@bottomnumber ... 404
\c@chapter ...
.... 638, 651, 1053,
1067, 1078, 1097
\c@dbltopnumber ... 409
\c@enumi ... 942
\c@enumii ... 943
\c@enumiii ... 944
\c@enumiv 945, 1262, 1269
\c@equation . 1063, 1067
\c@figure ... 1071
\c@footnote ... 580, 1306
\c@paragraph ... 638, 656
\c@part ... 638, 648
\c@section ...
.... 638, 649, 652, 1046
\c@subparagraph 638, 657
\c@subsection ... 638, 654
\c@subsubsection ...
.... 638, 655
\c@table ... 1090
\c@tocdepth ...
.... 1153, 1172, 1189
\c@topnumber ... 401
\c@totalnumber ... 406
\cal ... 1130
\centering ... 739, 762
\changes ... 963
\chapter ... 781, 1144,
1225, 1241, 1259
\chaptermark ... 492,
521, 536, 630, 801
\chaptername . 658, 1321
\cleardoublepage ...
.... 662, 670, 678,
695, 782, 1013, 1027
\clearpage 664, 672,
680, 697, 782, 1297
\clubpenalty ...
.... 228, 1271, 1272
\col@number ... 586
\columnsep . 1295, 1329

\columnseprule	1294, 1330	\footnotesep	394	J	
\columnwidth	1304	\footnotesign	143, 546	\jot	1069
\contentsname	1144, 1146, 1148, 1313	\footskip	245, 390	L	
\cs	963	\fps@figure	1080	\l@chapter	1170
D		\fps@table	1099	\l@figure	1233, 1250
\date	540, 574, 608	\frontmatter	659	\l@paragraph	1206
\dblfloatpagefraction	411	\ftype@figure	1080	\l@part	1152
\dblfloatsep	428	\ftype@table	1099	\l@section	1187
\dbltextfloatsep	428	H		\l@subsection	1206
\dbltopfraction	410	\hb@xt@		\l@subsubsection	1206
\DeclareOldFontCommand	1123, 1124, 1125, 1126, 1127, 1128, 1129	583, 1120, 1162, 1182, 1199, 1310		\l@table	1250
\DeclareRobustCommand	1130, 1131	\headheight	236, 387	\labelenumi	946
description (environment)	957	\headsep	236, 388	\labelenumii	946
\descriptionlabel	959, 961	\Huge	177, 747, 765, 821, 835	\labelenumiii	946
\displaywidowpenalty	230	\huge	177, 724, 743, 755, 815	\labelenumiv	946
\doublerulesep	1058	I		\labelitemi	953
E		\if@compatibility		\labelitemii	953
\endquotation	987	\if@mainmatter	8, 495, 524, 788, 814	\labelitemiii	953
\endtitlepage	975	\if@noskipsec	686	\labelitemiv	953
environments:		\if@openright	7, 661, 669, 677, 694, 771, 782	\labelsep	875, 908, 924, 933, 936, 939, 961, 1059, 1265
abstract	963	\if@restonecol	3, 1022, 1036, 1150,	\labelwidth	875, 907, 908, 923, 924, 932, 933, 935, 936, 938, 939, 958, 1263, 1264
description	957	1023, 1231, 1248, 1297		\LARGE	177, 552, 617
figure	1084	1231, 1248, 1297		\Large	177, 721, 842
figure*	1084	1231, 1248, 1297		\large	177, 554, 560, 619, 625, 846, 1162
quotation	999	1231, 1248, 1297		\leftmargin	
quote	1006	1231, 1248, 1297		67, 116, 126, 136, 149, 159, 169, 859, 888, 906, 922, 931, 934, 937, 958, 995, 996, 1002, 1007, 1264, 1265
table	1103	1231, 1248, 1297		\leftmargini	116, 126, 136, 149, 159, 169, 859, 876, 888
table*	1103	1231, 1248, 1297		\leftmarginii	
thebibliography	1253	1231, 1248, 1297		859, 906, 907
theindex	1282	1231, 1248, 1297		\leftmarginiii	
titlepage	1010	1231, 1248, 1297		859, 922, 923
verse	990	1231, 1248, 1297		\leftmarginiv	
\evensidemargin	309	1231, 1248, 1297		859, 931, 932
\ext@figure	1080	1231, 1248, 1297		\leftmarginv	
\ext@table	1099	1231, 1248, 1297		859, 934, 935
F		\indexname	1288, 1289, 1290, 1291, 1316	\leftmarginvi	
\fboxrule	1061	\indexspace	1301	859, 937, 938
\fboxsep	1061	\interlinepenalty		\leftskip	1180, 1181, 1197, 1198
figure (environment)	1084	233, 718, 740, 753, 763, 820, 834	\lineskip	204, 555, 620
figure* (environment)	1084	1014, 1028, 1139, 1220, 1236, 1283, 1338	\listfigurename	
\figurename	1083, 1319	\it	1127	1225, 1227, 1228, 1229, 1313
\floatpagefraction	408	\item	997, 1004, 1008, 1296	\listoffigures	1218
\floatsep	413	\itemindent	68, 69, 958, 993, 994, 1001	\listoftables	1234
\flushbottom	1341	\itemsep	119, 129, 139, 152, 162, 172, 892, 897, 902, 921, 930, 992		
\fnum@figure	1083	\itshape	1127		
\fnum@table	1102				
\footins	397, 1060				
\footnote	548, 616				
\footnoterule	547, 1302				

\listparindent	69, 994, 1000, 1001	\pagenumbering	667, 675, 1333	\subsectionmark	484, 538, 630
\listtablename	1241, 1243, 1245, 1246, 1313	\paperheight	11, 14, 17, 20, 23, 26, 29, 30, 291, 385	\subsubitem	1298
M		\paperwidth	12, 15, 18, 21, 24, 27, 30, 31, 263, 351, 359, 373	\subsubsectionmark	847
\mainmatter	668	\paragraph	851	\subsubsubsectionmark	630
\makelabel	959	\paragraphmark	630	T	
\maketitle	544	\parindent 208, 582, 717, 752, 812, 832, 855, 1159, 1177, 1194, 1292, 1308	\tabbingsep	1059
\MakeUppercase 479,	493, 501, 514, 522, 1148, 1228, 1229, 1245, 1246, 1256, 1260, 1290, 1291	\parsep	70, 118, 119, 128, 129, 138, 139, 151, 152, 161, 162, 171, 172, 890, 895	\tabcolsep	1056
\marginparpush	299	\part	684	table (environment)	1103
\marginparsep	299, 356, 364	\partname	721, 743, 1321	table* (environment)	1103
\marginparwidth	309	\partopsep	878, 929	\tablename	1102, 1319
\mathbf	1126	\postdisplaypenalty	230	\tableofcontents	1137
\mathcal	1130	\predisplaypenalty	230	\textasteriskcentered	955
\mathit	1127	\ps@headings	471	\textbullet	953
\mathnormal	1131	\ps@myheadings	531	\textendash	954
\mathrm	1123	Q		\textfloatsep	413
\mathsf	1124	\quad	481, 487, 516	\textfraction	407
\mathtt	1125	\quotation	985	\textheight	285, 389
\maxdepth	249	quotation (environment)	999	\textperiodcentered	956
\medskipamount	219	quote (environment)	1006	\textwidth 251, 352, 360, 375
\mit	1130	R		\thanks	548, 566, 599, 616
N		\refname	1255, 1256, 1316	thebibliography (environment)	1253
\newblock	72, 1278	\rm	1123	\thechapter	496,
\newif	3, 4, 7, 8	S		525, 648, 790,	
\nobreakspace	721, 743, 1083, 1102	\sbox	1115	792, 815, 1053,	
\normalfont	581, 584, 719, 741, 754, 764, 812, 833, 842, 846, 850, 854, 858, 954, 962, 1123, 1124, 1125, 1126, 1127, 1128, 1129, 1312	\sc	1127	1067, 1078, 1097	
\normallineskip	204	\scriptsize	177	\theenumi 941, 946, 950, 951
\normalsize 87, 850, 854, 858	\scshape	1129	\theenumii	941, 947, 951
\num@figure	1080	\section	839,	\theenumiii	941, 948, 952
\num@table	1099	979, 1146, 1227, 1243, 1255, 1288	\sectionmark	941, 949, 1269	
O		\sf	478, 500, 513, 537, 630	\theenumiv	1063, 1070
\oddsidemargin	309	\sffamily	1123	\theequation	1073, 1077, 1083
\onecolumn	701, 1015, 1029, 1140, 1221, 1237, 1297, 1343	\sl	1124	\thefigure 1073, 1077, 1083
\overfullrule	44, 46	\small	110, 546, 981	\thefootnote	580
P		\smallskipamount	219	theindex (environment)	1282
\p@enumui	950	\subitem	1298	\thepage	474,
\p@enumiii	950	\subparagraph	855	475, 510, 533, 534	
\p@enumiv	950, 1268	\subparagraphmark	630	\theparagraph	648

\topmargin	379	\tt	1123	V
\topsep	117 , 127 , 137 ,	\ttfamily	1125	verse (environment) . 990
150,	160,	170,	\twocolumn	
891,	896,	901,	589, 778 , 1022 ,	
910,	914,	918,	1036, 1150,	W
925,	926,	927,	1231, 1248,	
\topskip .. 236 , 250 , 298			1288, 1289, 1339	\widowpenalty 228 , 1273