

util-vserver (libvserver) Reference Manual
0.30.216-pre2883

Generated by Doxygen 1.5.1

Fri May 7 06:17:14 2010

Contents

1	util-vserver (libvserver) Module Index	1
2	util-vserver (libvserver) Data Structure Index	1
3	util-vserver (libvserver) File Index	2
4	util-vserver (libvserver) Module Documentation	2
5	util-vserver (libvserver) Data Structure Documentation	10
6	util-vserver (libvserver) File Documentation	19

1 util-vserver (libvserver) Module Index

1.1 util-vserver (libvserver) Modules

Here is a list of all modules:

Syscall wrappers	2
Helper functions	8

2 util-vserver (libvserver) Data Structure Index

2.1 util-vserver (libvserver) Data Structures

Here are the data structures with brief descriptions:

Mapping_uint32	10
Mapping_uint64	11
vc_ctx_caps (Capabilities of process-contexts)	11
vc_ctx_dlimit	12
vc_ctx_flags (Flags of process-contexts)	12
vc_ctx_stat (Statistics about a context)	13
vc_err_listparser (Information about parsing errors)	13
vc_ip_mask_pair	14
vc_net_addr	14
vc_net_caps	14

vc_net_flags	15
vc_nx_info	15
vc_rlimit (The limits of a resources)	15
vc_rlimit_mask (Masks describing the supported limits)	16
vc_rlimit_stat (Statistics for a resource limit)	16
vc_sched_info	17
vc_set_sched	17
vc_virt_stat (Contains further statistics about a context)	18
vc_vx_info	18

3 util-vserver (libvserver) File Index

3.1 util-vserver (libvserver) File List

Here is a list of all documented files with brief descriptions:

internal.h (Declarations which are used by util-vserver internally)	19
vserver.h (The public interface of the the libvserver library)	20

4 util-vserver (libvserver) Module Documentation

4.1 Syscall wrappers

Functions

- [int vc_syscall](#) (uint32_t cmd, [xid_t](#) xid, void *data)
The generic vserver syscall.
- [int vc_get_version](#) ()
Returns the version of the current kernel API.
- [vc_vci_t vc_get_vci](#) ()
Returns the kernel configuration bits.
- [xid_t vc_new_s_context](#) ([xid_t](#) ctx, unsigned int remove_cap, unsigned int flags)
Moves current process into a context.
- [int vc_set_ipv4root](#) (uint32_t bcast, size_t nb, struct [vc_ip_mask_pair](#) const *ips)
Sets the ipv4root information.
- [xid_t vc_ctx_create](#) ([xid_t](#) xid, struct [vc_ctx_flags](#) *flags)

Creates a context without starting it.

- `int vc_ctx_migrate (xid_t xid, uint_least64_t flags)`
Moves the current process into the specified context.
- `int vc_ctx_stat (xid_t xid, struct vc_ctx_stat *stat)`
Get some statistics about a context.
- `int vc_virt_stat (xid_t xid, struct vc_virt_stat *stat)`
Get more statistics about a context.
- `int vc_ctx_kill (xid_t ctx, pid_t pid, int sig)`
Sends a signal to a context/pid.
- `xid_t vc_get_task_xid (pid_t pid)`
Returns the context of the given process.
- `int vc_wait_exit (xid_t xid)`
Waits for the end of a context.
- `int vc_get_rlimit (xid_t xid, int resource, struct vc_rlimit *lim)`
Returns the limits of resource.
- `int vc_set_rlimit (xid_t xid, int resource, struct vc_rlimit const *lim)`
Sets the limits of resource.
- `int vc_rlimit_stat (xid_t xid, int resource, struct vc_rlimit_stat *stat)`
Returns the current stats of resource.
- `int vc_reset_minmax (xid_t xid)`
Resets the minimum and maximum observed values of all resources.
- `int vc_get_iattr (char const *filename, xid_t *xid, uint_least32_t *flags, uint_least32_t *mask)`
Returns information about attributes and assigned context of a file.
- `xid_t vc_getfilecontext (char const *filename)`
Returns the context of filename.

4.1.1 Detailed Description

Functions which are calling the vserver syscall directly.

4.1.2 Function Documentation

4.1.2.1 `xid_t vc_ctx_create (xid_t xid, struct vc_ctx_flags *flags)`

Creates a context without starting it.

This functions initializes a new context. When already in a freshly created context, this old context will be discarded.

Parameters:

xid The new context; special values are:

- VC_DYNAMIC_XID which means to create a dynamic context

Returns:

the xid of the created context, or VC_NOCTX on errors. `errno` will be set appropriately.

4.1.2.2 int vc_ctx_kill (xid_t ctx, pid_t pid, int sig)

Sends a signal to a context/pid.

Special values for *pid* are:

- -1 which means every process in ctx except the init-process
- 0 which means every process in ctx inclusive the init-process

4.1.2.3 int vc_ctx_migrate (xid_t xid, uint_least64_t flags)

Moves the current process into the specified context.

Parameters:

xid The new context

flags The flags, see VC_VXM_*

Returns:

0 on success, -1 on errors

4.1.2.4 int vc_ctx_stat (xid_t xid, struct vc_ctx_stat * stat)

Get some statistics about a context.

Parameters:

xid The context to get stats about

stat Where to store the result

Returns:

0 on success, -1 on errors.

4.1.2.5 int vc_get_iattr (char const * filename, xid_t * xid, uint_least32_t * flags, uint_least32_t * mask)

Returns information about attributes and assigned context of a file.

This function returns the VC_IATTR_XXX flags and about the assigned context of a file. To request an information, the appropriate bit in `mask` must be set and the corresponding parameter (*xid* or *flags*) must not be NULL.

E.g. to receive the assigned context, the VC_IATTR_XID bit must be set in *mask*, and *xid* must point to valid memory.

Possible flags are VC_IATTR_ADMIN, VC_IATTR_WATCH , VC_IATTR_HIDE, VC_IATTR_BARRIER, VC_IATTR_IUNLINK and VC_IATTR_IMMUTABLE.

Parameters:

filename The name of the file whose attributes shall be determined.

xid When non-zero and the VC_IATTR_XID bit is set in *mask*, the assigned context of *filename* will be stored there.

flags When non-zero, a bitmask of current attributes will be stored there. These attributes must be requested explicitly by setting the appropriate bit in *mask*

mask Points to a bitmask which tells which attributes shall be determined. On return, it will masquerade the attributes which were determined.

Precondition:

```
mask!=0 && !((*mask&VC_IATTR_XID) && xid==0) && !((*mask&~VC_IATTR_XID) && flags==0)
```

4.1.2.6 int vc_get_rlimit (xid_t xid, int resource, struct vc_rlimit * lim)

Returns the limits of *resource*.

Parameters:

xid The id of the context

resource The resource which will be queried

lim The result which will be filled with the limits

Returns:

0 on success, and -1 on errors.

4.1.2.7 xid_t vc_get_task_xid (pid_t pid)

Returns the context of the given process.

Parameters:

pid the process-id whose xid shall be determined; pid==0 means the current process.

Returns:

the xid of process *pid* or -1 on errors

4.1.2.8 vc_vci_t vc_get_vci ()

Returns the kernel configuration bits.

Returns:

The kernel configuration bits

4.1.2.9 `int vc_get_version ()`

Returns the version of the current kernel API.

Returns:

The versionnumber of the kernel API

4.1.2.10 `xid_t vc_getfilecontext (char const *filename)`

Returns the context of `filename`.

This function calls `vc_get_iattr()` with appropriate arguments to determine the context of `filename`. In error-case or when no context is assigned, `VC_NOCTX` will be returned. To differ between both cases, `errno` must be examined.

WARNING: this function can modify `errno` although no error happened.

Parameters:

filename The file to check

Returns:

The assigned context, or `VC_NOCTX` when an error occurred or no such assignment exists. `errno` will be 0 in the latter case

4.1.2.11 `xid_t vc_new_s_context (xid_t ctx, unsigned int remove_cap, unsigned int flags)`

Moves current process into a context.

Puts current process into context `ctx`, removes the capabilities given in `remove_cap` and sets `flags`.

Parameters:

ctx The new context; special values for are

- `VC_SAMECTX` which means the current context (just for changing caps and flags)
- `VC_DYNAMIC_XID` which means the next free context; this value can be used by ordinary users also

remove_cap The linux capabilities which will be **removed**.

flags Special flags which will be set.

Returns:

The new context-id, or `VC_NOCTX` on errors; `errno` will be set appropriately

See <http://vserver.13thfloor.at/Stuff/Logic.txt> for details

4.1.2.12 `int vc_reset_minmax (xid_t xid)`

Resets the minimum and maximum observed values of all resources.

Parameters:

xid The id of the context

Returns:

0 on success, and -1 on errors.

4.1.2.13 `int vc_rlimit_stat (xid_t xid, int resource, struct vc_rlimit_stat * stat)`

Returns the current stats of *resource*.

Parameters:

xid The id of the context
resource The resource which will be queried
stat The result which will be filled with the stats

Returns:

0 on success, and -1 on errors.

4.1.2.14 `int vc_set_ipv4root (uint32_t bcast, size_t nb, struct vc_ip_mask_pair const * ips)`

Sets the ipv4root information.

Precondition:

$nb < \text{NB_IPV4ROOT}$ && $ips \neq 0$

4.1.2.15 `int vc_set_rlimit (xid_t xid, int resource, struct vc_rlimit const * lim)`

Sets the limits of *resource*.

Parameters:

xid The id of the context
resource The resource which will be queried
lim The new limits

Returns:

0 on success, and -1 on errors.

4.1.2.16 `int vc_syscall (uint32_t cmd, xid_t xid, void * data)`

The generic vserver syscall.

This function executes the generic vserver syscall. It uses the correct syscallnumber (which may differ between the different architectures).

Parameters:

cmd the command to be executed
xid the xid on which the cmd shall be applied
data additional arguments; depends on *cmd*

Returns:

depends on *cmd*; usually, -1 stands for an error

4.1.2.17 int `vc_virt_stat` (`xid_t` *xid*, struct `vc_virt_stat` * *stat*)

Get more statistics about a context.

Parameters:

- xid* The context to get stats about
- stat* Where to store the result

Returns:

0 on success, -1 on errors.

4.2 Helper functions

Data Structures

- struct `vc_err_listparser`
Information about parsing errors.

Functions

- `size_t` `vc_get_nb_ipv4root` () VC_ATTR_CONST
Returns the value of NB_IPV4ROOT.
- `bool` `vc_parseLimit` (char const *str, `vc_limit_t` *res)
Parses a string describing a limit.
- `uint_least64_t` `vc_text2bcap` (char const *str, `size_t` len)
Converts a single string into bcapability.
- char const * `vc_lobcap2text` (`uint_least64_t` *val)
Converts the lowest bit of a bcapability or the entire value (when possible) to a textual representation.
- `int` `vc_list2bcap` (char const *str, `size_t` len, struct `vc_err_listparser` *err, struct `vc_ctx_caps` *cap)
Converts a string into a bcapability-bitmask.

4.2.1 Detailed Description

Functions which are doing general helper tasks like parameter parsing.

4.2.2 Function Documentation

4.2.2.1 `size_t` `vc_get_nb_ipv4root` ()

Returns the value of NB_IPV4ROOT.

This function returns the value of NB_IPV4ROOT which was used when the library was built, but **not** the value which is used by the currently running kernel.

4.2.2.2 `int vc_list2bcap (char const * str, size_t len, struct vc_err_listparser * err, struct vc_ctx_caps * cap)`

Converts a string into a bcapability-bitmask.

Syntax of *str*: list2xxx.syntax

When the '~' prefix is used, the bits will be unset and a '~' after another '~' will cancel both ones. The '^' prefix specifies a bitnumber instead of a bitmask.

"literal name" is everything which will be accepted by the `vc_text2bcap()` function. The special values for NAME will be recognized case insensitively

Parameters:

str The string to be parsed

len The length of the string, or 0 for automatic detection

err Pointer to a structure for error-information, or NULL.

cap Pointer to a `vc_ctx_caps` structure holding the results; only the *bcaps* and *bmask* fields will be changed and already set values will not be honored. When an error occurred, *cap* will have the value of all processed valid BCAP parts.

Returns:

0 on success, -1 on error. In error case, *err* will hold position and length of the first not understood BCAP part

Precondition:

str != 0 && *cap* != 0; *cap*->*bcaps* and *cap*->*bmask* must be initialized

4.2.2.3 `char const* vc_lobcap2text (uint_least64_t * val)`

Converts the lowest bit of a bcapability or the entire value (when possible) to a textual representation.

Parameters:

val The string to be converted; on success, the detected bit(s) will be unset, in errorcase only the lowest set bit

Returns:

A textual representation of *val* resp. of its lowest set bit; or NULL in errorcase.

Precondition:

val != 0

Postcondition:

**val_{old}* != 0 <-> **val_{old}* > **val_{new}*
**val_{old}* == 0 --> *result* == 0

4.2.2.4 bool vc_parseLimit (char const * *str*, vc_limit_t * *res*)

Parses a string describing a limit.

This function parses *str* and interprets special words like "inf" or suffixes. Valid suffixes are

- k ... 1000
- m ... 1000000
- K ... 1024
- M ... 1048576

Parameters:

str The string which shall be parsed

res Will be filled with the interpreted value; in errorcase, this value is undefined.

Returns:

true, iff the string *str* could be parsed. *res* will be filled with the interpreted value in this case.

Precondition:

str!=0 && *res*!=0

4.2.2.5 uint_least64_t vc_text2bcap (char const * *str*, size_t *len*)

Converts a single string into bcapability.

Parameters:

str The string to be parsed; both "CAP_XXX" and "XXX" will be accepted

len The length of the string, or 0 for automatic detection

Returns:

0 on error; a bitmask on success

Precondition:

str != 0

5 util-vserver (libvserver) Data Structure Documentation

5.1 Mapping_uint32 Struct Reference

Data Fields

- char const *const *id*
- size_t *len*
- uint_least32_t *val*

5.1.1 Detailed Description

Definition at line 80 of file internal.h.

The documentation for this struct was generated from the following file:

- [internal.h](#)

5.2 Mapping_uint64 Struct Reference

Data Fields

- char const *const [id](#)
- size_t [len](#)
- uint_least64_t [val](#)

5.2.1 Detailed Description

Definition at line 86 of file internal.h.

The documentation for this struct was generated from the following file:

- [internal.h](#)

5.3 vc_ctx_caps Struct Reference

Capabilities of process-contexts.

```
#include <vserver.h>
```

Data Fields

- uint_least64_t [bcaps](#)
Mask of set common system capabilities.
- uint_least64_t [bmask](#)
Mask of set and unset common system capabilities when used by set operations, or the modifiable capabilities when used by get operations.
- uint_least64_t [ccaps](#)
Mask of set process context capabilities.
- uint_least64_t [cmask](#)
Mask of set and unset process context capabilities when used by set operations, or the modifiable capabilities when used by get operations.

5.3.1 Detailed Description

Capabilities of process-contexts.

Definition at line 504 of file `vserver.h`.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.4 `vc_ctx_dlimit` Struct Reference

Data Fields

- `uint_least32_t` [space_used](#)
- `uint_least32_t` [space_total](#)
- `uint_least32_t` [inodes_used](#)
- `uint_least32_t` [inodes_total](#)
- `uint_least32_t` [reserved](#)

5.4.1 Detailed Description

Definition at line 781 of file `vserver.h`.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.5 `vc_ctx_flags` Struct Reference

Flags of process-contexts.

```
#include <vserver.h>
```

Data Fields

- `uint_least64_t` [flagword](#)
Mask of set context flags.
- `uint_least64_t` [mask](#)
Mask of set and unset context flags when used by set operations, or modifiable flags when used by get operations.

5.5.1 Detailed Description

Flags of process-contexts.

Definition at line 426 of file `vserver.h`.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.6 vc_ctx_stat Struct Reference

Statistics about a context.

```
#include <vserver.h>
```

Data Fields

- `uint_least32_t usecnt`
number of uses
- `uint_least32_t tasks`
number of tasks

5.6.1 Detailed Description

Statistics about a context.

Definition at line 457 of file `vserver.h`.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.7 vc_err_listparser Struct Reference

Information about parsing errors.

```
#include <vserver.h>
```

Data Fields

- `char const * ptr`
Pointer to the first character of an erroneous string.
- `size_t len`
Length of the erroneous string.

5.7.1 Detailed Description

Information about parsing errors.

Definition at line 856 of file `vserver.h`.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.8 vc_ip_mask_pair Struct Reference

Data Fields

- uint32_t [ip](#)
- uint32_t [mask](#)

5.8.1 Detailed Description

Definition at line 404 of file vserver.h.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.9 vc_net_addr Struct Reference

Data Fields

- uint16_t [vna_type](#)
- uint16_t [vna_flags](#)
- uint16_t [vna_prefix](#)
- uint16_t [vna_parent](#)
- struct {
 - union {
 - [in_addr v4](#)
 - [in6_addr v6](#)
 - ip**
 - union {
 - [in_addr v4](#)
 - [in6_addr v6](#)
 - ip2**
 - union {
 - [in_addr v4](#)
 - [in6_addr v6](#)
 - mask**
- s**

5.9.1 Detailed Description

Definition at line 654 of file vserver.h.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.10 vc_net_caps Struct Reference

Data Fields

- uint_least64_t [ncaps](#)

- [uint_least64_t cmask](#)

5.10.1 Detailed Description

Definition at line 695 of file `vserver.h`.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.11 `vc_net_flags` Struct Reference

Data Fields

- [uint_least64_t flagword](#)
- [uint_least64_t mask](#)

5.11.1 Detailed Description

Definition at line 681 of file `vserver.h`.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.12 `vc_nx_info` Struct Reference

Data Fields

- [nid_t nid](#)

5.12.1 Detailed Description

Definition at line 647 of file `vserver.h`.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.13 `vc_rlimit` Struct Reference

The limits of a resources.

```
#include <vserver.h>
```

Data Fields

- [vc_limit_t min](#)
the guaranted minimum of a resources

- [vc_limit_t soft](#)
the softlimit of a resource
- [vc_limit_t hard](#)
the absolute hardlimit of a resource

5.13.1 Detailed Description

The limits of a resources.

This is a triple consisting of a minimum, soft and hardlimit.

Definition at line 570 of file `vserver.h`.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.14 `vc_rlimit_mask` Struct Reference

Masks describing the supported limits.

```
#include <vserver.h>
```

Data Fields

- [uint_least32_t min](#)
masks the resources supporting a minimum limit
- [uint_least32_t soft](#)
masks the resources supporting a soft limit
- [uint_least32_t hard](#)
masks the resources supporting a hard limit

5.14.1 Detailed Description

Masks describing the supported limits.

Definition at line 557 of file `vserver.h`.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.15 `vc_rlimit_stat` Struct Reference

Statistics for a resource limit.

```
#include <vserver.h>
```

Data Fields

- [uint_least32_t hits](#)
number of hits on the limit
- [vc_limit_t value](#)
current value
- [vc_limit_t minimum](#)
minimum value observed
- [vc_limit_t maximum](#)
maximum value observed

5.15.1 Detailed Description

Statistics for a resource limit.

Definition at line 598 of file vserver.h.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.16 vc_sched_info Struct Reference

Data Fields

- [int_least32_t cpu_id](#)
- [int_least32_t bucket_id](#)
- [uint_least64_t user_msec](#)
- [uint_least64_t sys_msec](#)
- [uint_least64_t hold_msec](#)
- [uint_least32_t token_usec](#)
- [int_least32_t vavavoom](#)

5.16.1 Detailed Description

Definition at line 833 of file vserver.h.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.17 vc_set_sched Struct Reference

Data Fields

- [uint_least32_t set_mask](#)
- [int_least32_t fill_rate](#)

- [int_least32_t interval](#)
- [int_least32_t fill_rate2](#)
- [int_least32_t interval2](#)
- [int_least32_t tokens](#)
- [int_least32_t tokens_min](#)
- [int_least32_t tokens_max](#)
- [int_least32_t priority_bias](#)
- [int_least32_t cpu_id](#)
- [int_least32_t bucket_id](#)

5.17.1 Detailed Description

Definition at line 816 of file vserver.h.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.18 vc_virt_stat Struct Reference

Contains further statistics about a context.

```
#include <vserver.h>
```

Data Fields

- [uint_least64_t offset](#)
- [uint_least64_t uptime](#)
- [uint_least32_t nr_threads](#)
- [uint_least32_t nr_running](#)
- [uint_least32_t nr_uninterruptible](#)
- [uint_least32_t nr_onhold](#)
- [uint_least32_t nr_forks](#)
- [uint_least32_t load](#) [3]

5.18.1 Detailed Description

Contains further statistics about a context.

Definition at line 472 of file vserver.h.

The documentation for this struct was generated from the following file:

- [vserver.h](#)

5.19 vc_vx_info Struct Reference

Data Fields

- [xid_t xid](#)
- [pid_t initpid](#)

5.19.1 Detailed Description

Definition at line 522 of file vserver.h.

The documentation for this struct was generated from the following file:

- [vserver.h](#)


6 util-vserver (libvserver) File Documentation

6.1 internal.h File Reference

Declarations which are used by util-vserver internally.

```
#include "fmt.h"
#include "vserver.h"
#include <stdlib.h>
#include <stdbool.h>
```

Include dependency graph for internal.h:



Data Structures

- struct [Mapping_uint32](#)
- struct [Mapping_uint64](#)

Defines

- `#define _symbol_version(real, name, version)`
- `#define _default_symbol_version(real, name, version) extern __typeof (real) name __attribute__((alias (#name)))`
- `#define symbol_version(real, name, version) _symbol_version(real, name, version)`
- `#define default_symbol_version(real, name, version) _default_symbol_version(real, name, version)`

Functions

- `char * vc_getVserverByCtx_Internal (xid_t ctx, vcCfgStyle *style, char const *revdir, bool validate_result)`

- int **utilvserver_checkCompatVersion** ()
- uint_least32_t **utilvserver_checkCompatConfig** ()
- bool **utilvserver_isDirectory** (char const *path, bool follow_link)
- bool **utilvserver_isFile** (char const *path, bool follow_link)
- bool **utilvserver_isLink** (char const *path)
- int **utilvserver_listparser_uint32** (char const *str, size_t len, char const **err_ptr, size_t *err_len, uint_least32_t *flag, uint_least32_t *mask, uint_least32_t(*func)(char const *, size_t, bool *)) NONNULL((1
- int **utilvserver_listparser_uint64** (char const *str, size_t len, char const **err_ptr, size_t *err_len, uint_least64_t *flag, uint_least64_t *mask, uint_least64_t(*func)(char const *, size_t, bool *)) NONNULL((1
- ssize_t **utilvserver_value2text_uint32** (char const *str, size_t len, struct [Mapping_uint32](#) const *map, size_t map_len) NONNULL((1
- ssize_t **utilvserver_value2text_uint64** (char const *str, size_t len, struct [Mapping_uint64](#) const *map, size_t map_len) NONNULL((1
- ssize_t **utilvserver_text2value_uint32** (uint_least32_t *val, struct [Mapping_uint32](#) const *map, size_t map_len) NONNULL((1
- ssize_t **utilvserver_text2value_uint64** (uint_least64_t *val, struct [Mapping_uint64](#) const *map, size_t map_len) NONNULL((1

6.1.1 Detailed Description

Declarations which are used by util-vserver internally.


Definition in file [internal.h](#).

6.2 vserver.h File Reference

The public interface of the the libvserver library.

```
#include <stdint.h>
#include <stdlib.h>
#include <stdbool.h>
#include <sys/types.h>
#include <sched.h>
#include <netinet/in.h>
```

Include dependency graph for vserver.h:



This graph shows which files directly or indirectly include this file:



Data Structures

- struct [vc_ip_mask_pair](#)
- struct [vc_ctx_flags](#)
Flags of process-contexts.
- struct [vc_ctx_stat](#)
Statistics about a context.
- struct [vc_virt_stat](#)
Contains further statistics about a context.
- struct [vc_ctx_caps](#)
Capabilities of process-contexts.
- struct [vc_vx_info](#)
- struct [vc_rlimit_mask](#)
Masks describing the supported limits.
- struct [vc_rlimit](#)
The limits of a resources.
- struct [vc_rlimit_stat](#)
Statistics for a resource limit.
- struct [vc_nx_info](#)
- struct [vc_net_addr](#)
- struct [vc_net_flags](#)
- struct [vc_net_caps](#)
- struct [vc_ctx_dlimit](#)
- struct [vc_set_sched](#)
- struct [vc_sched_info](#)
- struct [vc_err_listparser](#)
Information about parsing errors.

Defines

- #define [VC_NOCTX](#) ((xid_t)(-1))
- #define [VC_NOXID](#) ((xid_t)(-1))
- #define [VC_DYNAMIC_XID](#) ((xid_t)(-1))
- #define [VC_SAMECTX](#) ((xid_t)(-2))
- #define [VC_NONID](#) ((nid_t)(-1))
- #define [VC_DYNAMIC_NID](#) ((nid_t)(-1))

- `#define VC_LIM_INFINITY (~0ULL)`
- `#define VC_LIM_KEEP (~1ULL)`
- `#define VC_CDLIM_UNSET (0U)`
- `#define VC_CDLIM_INFINITY (~0U)`
- `#define VC_CDLIM_KEEP (~1U)`
- `#define S_CTX_INFO_LOCK 1`
- `#define S_CTX_INFO_SCHED 2`
- `#define S_CTX_INFO_NPROC 4`
- `#define S_CTX_INFO_PRIVATE 8`
- `#define S_CTX_INFO_INIT 16`
- `#define S_CTX_INFO_HIDEINFO 32`
- `#define S_CTX_INFO_ULIMIT 64`
- `#define S_CTX_INFO_NAMESPACE 128`
- `#define VC_CAP_CHOWN 0`
- `#define VC_CAP_DAC_OVERRIDE 1`
- `#define VC_CAP_DAC_READ_SEARCH 2`
- `#define VC_CAP_FOWNER 3`
- `#define VC_CAP_FSETID 4`
- `#define VC_CAP_KILL 5`
- `#define VC_CAP_SETGID 6`
- `#define VC_CAP_SETUID 7`
- `#define VC_CAP_SETPCAP 8`
- `#define VC_CAP_LINUX_IMMUTABLE 9`
- `#define VC_CAP_NET_BIND_SERVICE 10`
- `#define VC_CAP_NET_BROADCAST 11`
- `#define VC_CAP_NET_ADMIN 12`
- `#define VC_CAP_NET_RAW 13`
- `#define VC_CAP_IPC_LOCK 14`
- `#define VC_CAP_IPC_OWNER 15`
- `#define VC_CAP_SYS_MODULE 16`
- `#define VC_CAP_SYS_RAWIO 17`
- `#define VC_CAP_SYS_CHROOT 18`
- `#define VC_CAP_SYS_PTRACE 19`
- `#define VC_CAP_SYS_PACCT 20`
- `#define VC_CAP_SYS_ADMIN 21`
- `#define VC_CAP_SYS_BOOT 22`
- `#define VC_CAP_SYS_NICE 23`
- `#define VC_CAP_SYS_RESOURCE 24`
- `#define VC_CAP_SYS_TIME 25`
- `#define VC_CAP_SYS_TTY_CONFIG 26`
- `#define VC_CAP_MKNOD 27`
- `#define VC_CAP_LEASE 28`
- `#define VC_CAP_AUDIT_WRITE 29`
- `#define VC_CAP_AUDIT_CONTROL 30`
- `#define VC_CAP_SETFCAP 31`
- `#define VC_CAP_MAC_OVERRIDE 32`
- `#define VC_CAP_MAC_ADMIN 33`
- `#define VC_IMMUTABLE_FILE_FL 0x0000010lu`
- `#define VC_IMMUTABLE_LINK_FL 0x0008000lu`
- `#define VC_IMMUTABLE_ALL (VC_IMMUTABLE_LINK_FL|VC_IMMUTABLE_FILE_FL)`

- #define [VC_IATTR_XID](#) 0x01000000u
- #define [VC_IATTR_ADMIN](#) 0x00000001u
- #define [VC_IATTR_WATCH](#) 0x00000002u
- #define [VC_IATTR_HIDE](#) 0x00000004u
- #define [VC_IATTR_WRITE](#) 0x00000008u
- #define [VC_IATTR_FLAGS](#) 0x0000000fu
- #define [VC_IATTR_BARRIER](#) 0x00010000u
- #define [VC_IATTR_IUNLINK](#) 0x00020000u
- #define [VC_IATTR_IMMUTABLE](#) 0x00040000u
- #define [VC_IATTR_COW](#) 0x00080000u
- #define [VC_VXF_INFO_LOCK](#) 0x00000001ull
- #define [VC_VXF_INFO_NPROC](#) 0x00000004ull
- #define [VC_VXF_INFO_PRIVATE](#) 0x00000008ull
- #define [VC_VXF_INFO_INIT](#) 0x00000010ull
- #define [VC_VXF_INFO_HIDEINFO](#) 0x00000020ull
- #define [VC_VXF_INFO_ULIMIT](#) 0x00000040ull
- #define [VC_VXF_INFO_NAMESPACE](#) 0x00000080ull
- #define [VC_VXF_SCHED_HARD](#) 0x00000100ull
- #define [VC_VXF_SCHED_PRIO](#) 0x00000200ull
- #define [VC_VXF_SCHED_PAUSE](#) 0x00000400ull
- #define [VC_VXF_VIRT_MEM](#) 0x00010000ull
- #define [VC_VXF_VIRT_UPTIME](#) 0x00020000ull
- #define [VC_VXF_VIRT_CPU](#) 0x00040000ull
- #define [VC_VXF_VIRT_LOAD](#) 0x00080000ull
- #define [VC_VXF_VIRT_TIME](#) 0x00100000ull
- #define [VC_VXF_HIDE_MOUNT](#) 0x01000000ull
- #define [VC_VXF_HIDE_NETIF](#) 0x02000000ull
- #define [VC_VXF_HIDE_VINFO](#) 0x04000000ull
- #define [VC_VXF_STATE_SETUP](#) (1ULL<<32)
- #define [VC_VXF_STATE_INIT](#) (1ULL<<33)
- #define [VC_VXF_STATE_ADMIN](#) (1ULL<<34)
- #define [VC_VXF_SC_HELPER](#) (1ULL<<36)
- #define [VC_VXF_REBOOT_KILL](#) (1ULL<<37)
- #define [VC_VXF_PERSISTENT](#) (1ULL<<38)
- #define [VC_VXF_FORK_RSS](#) (1ULL<<48)
- #define [VC_VXF_PROLIFIC](#) (1ULL<<49)
- #define [VC_VXF_IGNEG_NICE](#) (1ULL<<52)
- #define [VC_VXF_IGNEG_IONICE](#) (1ULL<<53)
- #define [VC_VXC_SET_UTSNAME](#) 0x00000001ull
- #define [VC_VXC_SET_RLIMIT](#) 0x00000002ull
- #define [VC_VXC_FS_SECURITY](#) 0x00000004ull
- #define [VC_VXC_TIOCSTI](#) 0x00000010ull
- #define [VC_VXC_RAW_ICMP](#) 0x00000100ull
- #define [VC_VXC_SYSLOG](#) 0x00001000ull
- #define [VC_VXC_OOM_ADJUST](#) 0x00002000ull
- #define [VC_VXC_AUDIT_CONTROL](#) 0x00004000ull
- #define [VC_VXC_SECURE_MOUNT](#) 0x00010000ull
- #define [VC_VXC_SECURE_REMOUNT](#) 0x00020000ull
- #define [VC_VXC_BINARY_MOUNT](#) 0x00040000ull
- #define [VC_VXC_QUOTA_CTL](#) 0x00100000ull

- #define [VC_VXC_ADMIN_MAPPER](#) 0x00200000ull
- #define [VC_VXC_ADMIN_CLOOP](#) 0x00400000ull
- #define [VC_VXC_KTHREAD](#) 0x01000000ull
- #define [VC_VXC_NAMESPACE](#) 0x02000000ull
- #define [VC_VXSM_FILL_RATE](#) 0x0001
- #define [VC_VXSM_INTERVAL](#) 0x0002
- #define [VC_VXSM_FILL_RATE2](#) 0x0004
- #define [VC_VXSM_INTERVAL2](#) 0x0008
- #define [VC_VXSM_TOKENS](#) 0x0010
- #define [VC_VXSM_TOKENS_MIN](#) 0x0020
- #define [VC_VXSM_TOKENS_MAX](#) 0x0040
- #define [VC_VXSM_PRIO_BIAS](#) 0x0100
- #define [VC_VXSM_CPU_ID](#) 0x1000
- #define [VC_VXSM_BUCKET_ID](#) 0x2000
- #define [VC_VXSM_IDLE_TIME](#) 0x0200
- #define [VC_VXSM_FORCE](#) 0x0400
- #define [VC_VXSM_MSEC](#) 0x4000
- #define [VC_VXSM_V3_MASK](#) 0x0173
- #define [VC_NXF_INFO_LOCK](#) 0x00000001ull
- #define [VC_NXF_INFO_PRIVATE](#) 0x00000008ull
- #define [VC_NXF_SINGLE_IP](#) 0x00000100ull
- #define [VC_NXF_LBACK_REMAP](#) 0x00000200ull
- #define [VC_NXF_LBACK_ALLOW](#) 0x00000400ull
- #define [VC_NXF_HIDE_NETIF](#) 0x02000000ull
- #define [VC_NXF_HIDE_LBACK](#) 0x04000000ull
- #define [VC_NXF_STATE_SETUP](#) (1ULL<<32)
- #define [VC_NXF_STATE_ADMIN](#) (1ULL<<34)
- #define [VC_NXF_SC_HELPER](#) (1ULL<<36)
- #define [VC_NXF_PERSISTENT](#) (1ULL<<38)
- #define [VC_NXC_TUN_CREATE](#) 0x00000001ull
- #define [VC_NXC_RAW_ICMP](#) 0x00000100ull
- #define [VC_VLIMIT_NSOCK](#) 16
- #define [VC_VLIMIT_OPENFD](#) 17
- #define [VC_VLIMIT_ANON](#) 18
- #define [VC_VLIMIT_SHMEM](#) 19
- #define [VC_VLIMIT_SEMARY](#) 20
- #define [VC_VLIMIT_NSEMS](#) 21
- #define [VC_VLIMIT_DENTRY](#) 22
- #define [VC_VLIMIT_MAPPED](#) 23
- #define [VC_VCI_NO_DYNAMIC](#) (1 << 0)
- #define [VC_VCI_SPACES](#) (1 << 10)
- #define [VC_VCI_NETV2](#) (1 << 11)
- #define [VC_VCI_PPTAG](#) (1 << 28)
- #define [VC_DATTR_CREATE](#) 0x00000001
- #define [VC_DATTR_OPEN](#) 0x00000002
- #define [VC_DATTR_REMAP](#) 0x00000010
- #define [VC_VXM_SET_INIT](#) 0x00000001
- #define [VC_VXM_SET_REAPER](#) 0x00000002
- #define [VC_NXA_TYPE_IPV4](#) 0x0001
- #define [VC_NXA_TYPE_IPV6](#) 0x0002

- #define `VC_NXA_TYPE_NONE` 0x0000
- #define `VC_NXA_TYPE_ANY` 0x00FF
- #define `VC_NXA_TYPE_ADDR` 0x0010
- #define `VC_NXA_TYPE_MASK` 0x0020
- #define `VC_NXA_TYPE_RANGE` 0x0040
- #define `VC_NXA_MOD_BCAST` 0x0100
- #define `VC_NXA_MOD_LBACK` 0x0200
- #define `CLONE_NEWNS` 0x00020000
- #define `CLONE_NEWUTS` 0x04000000
- #define `CLONE_NEWIPC` 0x08000000
- #define `CLONE_NEWUSER` 0x10000000
- #define `CLONE_NEWPID` 0x20000000
- #define `CLONE_NEWNET` 0x40000000
- #define `VC_BAD_PERSONALITY` ((uint_least32_t)(-1))
- #define `vna_v4_ip` s.ip.v4
- #define `vna_v4_ip2` s.ip2.v4
- #define `vna_v4_mask` s.mask.v4
- #define `vna_v6_ip` s.ip.v6
- #define `vna_v6_ip2` s.ip2.v6
- #define `vna_v6_mask` s.mask.v6
- #define `VC_LIMIT_VSERVER_NAME_LEN` 1024
- #define `vcSKEL_INTERFACES` 1u
- #define `vcSKEL_PKGMGMT` 2u
- #define `vcSKEL_FILESYSTEM` 4u

Typedefs

- typedef an_unsigned_integer_type `xid_t`
- typedef an_unsigned_integer_type `nid_t`
- typedef an_unsigned_integer_type `tag_t`
- typedef uint64_t `vc_vci_t`
- typedef uint_least64_t `vc_limit_t`

The type which is used for a single limit value.

Enumerations

- enum `vc_uts_type` {
`vcVHI_CONTEXT`, `vcVHI_SYSNAME`, `vcVHI_NODENAME`, `vcVHI_RELEASE`,
`vcVHI_VERSION`, `vcVHI_MACHINE`, `vcVHI_DOMAINNAME` }
- enum `vcFeatureSet` {
`vcFEATURE_VKILL`, `vcFEATURE_IATTR`, `vcFEATURE_RLIMIT`, `vcFEATURE_-COMPAT`,
`vcFEATURE_MIGRATE`, `vcFEATURE_NAMESPACE`, `vcFEATURE_SCHED`, `vcFEATURE_VINFO`,
`vcFEATURE_VHI`, `vcFEATURE_VSHELPER0`, `vcFEATURE_VSHELPER`, `vcFEATURE_-VWAIT`,
`vcFEATURE_VNET`, `vcFEATURE_VSTAT`, `vcFEATURE_PPTAG`, `vcFEATURE_-PIDSPACE`,
`vcFEATURE_SPACES`, `vcFEATURE_PERSISTENT`, `vcFEATURE_PIVOT_ROOT` }

- enum `vcXidType` {
 `vcTYPE_INVALID`, `vcTYPE_MAIN`, `vcTYPE_WATCH`, `vcTYPE_STATIC`,
 `vcTYPE_DYNAMIC` }
- enum `vcCfgStyle` {
 `vcCFG_NONE`, `vcCFG_AUTO`, `vcCFG_LEGACY`, `vcCFG_RECENT_SHORT`,
 `vcCFG_RECENT_FULL` }
- enum `vcCtxType` { `vcCTX_XID` = 1, `vcCTX_NID`, `vcCTX_TAG` }

Functions

- int `vc_syscall` (uint32_t cmd, xid_t xid, void *data)
 The generic vserver syscall.
- int `vc_get_version` ()
 Returns the version of the current kernel API.
- `vc_vci_t` `vc_get_vci` ()
 Returns the kernel configuration bits.
- xid_t `vc_new_s_context` (xid_t ctx, unsigned int remove_cap, unsigned int flags)
 Moves current process into a context.
- int `vc_set_ipv4root` (uint32_t bcast, size_t nb, struct `vc_ip_mask_pair` const *ips)
 Sets the ipv4root information.
- size_t `vc_get_nb_ipv4root` () VC_ATTR_CONST
 Returns the value of NB_IPV4ROOT.
- xid_t `vc_ctx_create` (xid_t xid, struct `vc_ctx_flags` *flags)
 Creates a context without starting it.
- int `vc_ctx_migrate` (xid_t xid, uint_least64_t flags)
 Moves the current process into the specified context.
- int `vc_ctx_stat` (xid_t xid, struct `vc_ctx_stat` *stat)
 Get some statistics about a context.
- int `vc_virt_stat` (xid_t xid, struct `vc_virt_stat` *stat)
 Get more statistics about a context.
- int `vc_ctx_kill` (xid_t ctx, pid_t pid, int sig)
 Sends a signal to a context/pid.
- int `vc_get_cflags` (xid_t xid, struct `vc_ctx_flags` *)
- int `vc_set_cflags` (xid_t xid, struct `vc_ctx_flags` const *)
- int `vc_get_ccaps` (xid_t xid, struct `vc_ctx_caps` *)
- int `vc_set_ccaps` (xid_t xid, struct `vc_ctx_caps` const *)
- int `vc_get_vx_info` (xid_t xid, struct `vc_vx_info` *info)
- xid_t `vc_get_task_xid` (pid_t pid)

Returns the context of the given process.

- `int vc_wait_exit (xid_t xid)`
Waits for the end of a context.
- `int vc_get_rlimit_mask (xid_t xid, struct vc_rlimit_mask *lim)`
Returns the limits supported by the kernel.
- `int vc_get_rlimit (xid_t xid, int resource, struct vc_rlimit *lim)`
Returns the limits of resource.
- `int vc_set_rlimit (xid_t xid, int resource, struct vc_rlimit const *lim)`
Sets the limits of resource.
- `int vc_rlimit_stat (xid_t xid, int resource, struct vc_rlimit_stat *stat)`
Returns the current stats of resource.
- `int vc_reset_minmax (xid_t xid)`
Resets the minimum and maximum observed values of all resources.
- `bool vc_parseLimit (char const *str, vc_limit_t *res)`
Parses a string describing a limit.
- `nid_t vc_get_task_nid (pid_t pid)`
- `int vc_get_nx_info (nid_t nid, struct vc_nx_info *)`
- `nid_t vc_net_create (nid_t nid)`
- `int vc_net_migrate (nid_t nid)`
- `int vc_net_add (nid_t nid, struct vc_net_addr const *info)`
- `int vc_net_remove (nid_t nid, struct vc_net_addr const *info)`
- `int vc_get_nflags (nid_t, struct vc_net_flags *)`
- `int vc_set_nflags (nid_t, struct vc_net_flags const *)`
- `int vc_get_ncaps (nid_t, struct vc_net_caps *)`
- `int vc_set_ncaps (nid_t, struct vc_net_caps const *)`
- `int vc_set_iattr (char const *filename, xid_t xid, uint_least32_t flags, uint_least32_t mask)`
- `int vc_fset_iattr (int fd, xid_t xid, uint_least32_t flags, uint_least32_t mask)`
- `int vc_get_iattr (char const *filename, xid_t *xid, uint_least32_t *flags, uint_least32_t *mask)`
Returns information about attributes and assigned context of a file.
- `int vc_fget_iattr (int fd, xid_t *xid, uint_least32_t *flags, uint_least32_t *mask)`
- `xid_t vc_getfilecontext (char const *filename)`
Returns the context of filename.
- `int vc_set_vhi_name (xid_t xid, vc_uts_type type, char const *val, size_t len)`
- `int vc_get_vhi_name (xid_t xid, vc_uts_type type, char *val, size_t len)`
- `int vc_enter_namespace (xid_t xid, uint_least64_t mask, uint32_t index)`
- `int vc_set_namespace (xid_t xid, uint_least64_t mask, uint32_t index)`
- `int vc_cleanup_namespace (void)`
- `uint_least64_t vc_get_space_mask (void)`
- `uint_least64_t vc_get_space_default (void)`
- `int vc_add_dlimit (char const *filename, xid_t xid, uint_least32_t flags)`

- int [vc_rem_dlimit](#) (char const *filename, [xid_t](#) xid, uint_least32_t flags)
- int [vc_set_dlimit](#) (char const *filename, [xid_t](#) xid, uint_least32_t flags, struct [vc_ctx_dlimit](#) const *limits)
- int [vc_get_dlimit](#) (char const *filename, [xid_t](#) xid, uint_least32_t flags, struct [vc_ctx_dlimit](#) *limits)
- [tag_t](#) [vc_get_task_tag](#) (pid_t pid)
- int [vc_tag_create](#) ([tag_t](#) tag)
- int [vc_tag_migrate](#) ([tag_t](#) tag)
- int [vc_set_sched](#) ([xid_t](#) xid, struct [vc_set_sched](#) const *)
- int [vc_get_sched](#) ([xid_t](#) xid, struct [vc_set_sched](#) *)
- int [vc_sched_info](#) ([xid_t](#) xid, struct [vc_sched_info](#) *info)
- int [vc_set_mapping](#) ([xid_t](#) xid, const char *device, const char *target, uint32_t flags)
- int [vc_unset_mapping](#) ([xid_t](#) xid, const char *device, const char *target, uint32_t flags)
- int [vc_get_badness](#) ([xid_t](#) xid, int64_t *badness)
- int [vc_set_badness](#) ([xid_t](#) xid, int64_t badness)
- uint_least64_t [vc_text2bcap](#) (char const *str, size_t len)

Converts a single string into bcapability.

- char const * [vc_lobcap2text](#) (uint_least64_t *val)
Converts the lowest bit of a bcapability or the entire value (when possible) to a textual representation.
- int [vc_list2bcap](#) (char const *str, size_t len, struct [vc_err_listparser](#) *err, struct [vc_ctx_caps](#) *cap)
Converts a string into a bcapability-bitmask.

- uint_least64_t [vc_text2ccap](#) (char const *, size_t len)
- char const * [vc_loccap2text](#) (uint_least64_t *)
- int [vc_list2ccap](#) (char const *, size_t len, struct [vc_err_listparser](#) *err, struct [vc_ctx_caps](#) *)
- int [vc_list2cflag](#) (char const *, size_t len, struct [vc_err_listparser](#) *err, struct [vc_ctx_flags](#) *flags)
- uint_least64_t [vc_text2cflag](#) (char const *, size_t len)
- char const * [vc_locflag2text](#) (uint_least64_t *)
- uint_least32_t [vc_list2cflag_compat](#) (char const *, size_t len, struct [vc_err_listparser](#) *err)
- uint_least32_t [vc_text2cflag_compat](#) (char const *, size_t len)
- char const * [vc_hicflag2text_compat](#) (uint_least32_t)
- int [vc_text2cap](#) (char const *)
- char const * [vc_cap2text](#) (unsigned int)
- int [vc_list2nflag](#) (char const *, size_t len, struct [vc_err_listparser](#) *err, struct [vc_net_flags](#) *flags)
- uint_least64_t [vc_text2nflag](#) (char const *, size_t len)
- char const * [vc_lonflag2text](#) (uint_least64_t *)
- uint_least64_t [vc_text2ncap](#) (char const *, size_t len)
- char const * [vc_loncap2text](#) (uint_least64_t *)
- int [vc_list2ncap](#) (char const *, size_t len, struct [vc_err_listparser](#) *err, struct [vc_net_caps](#) *)
- uint_least64_t [vc_get_insecurebcaps](#) () VC_ATTR_CONST
- uint_least32_t [vc_text2personalityflag](#) (char const *str, size_t len)
- char const * [vc_lopersonality2text](#) (uint_least32_t *)
- int [vc_list2personalityflag](#) (char const *, size_t len, uint_least32_t *personality, struct [vc_err_listparser](#) *err)
- uint_least32_t [vc_str2personalitytype](#) (char const *, size_t len)
- bool [vc_isSupported](#) ([vcFeatureSet](#)) VC_ATTR_CONST
- bool [vc_isSupportedString](#) (char const *)
- [vcXidType](#) [vc_getXIDType](#) ([xid_t](#) xid) VC_ATTR_CONST
- bool [vc_is_dynamic_xid](#) ([xid_t](#) xid)

- [xid_t vc_xidopt2xid](#) (char const *, bool honor_static, char const **err_info)
- [nid_t vc_nidopt2nid](#) (char const *, bool honor_static, char const **err_info)
- [tag_t vc_tagopt2tag](#) (char const *, bool honor_static, char const **err_info)
- [vcCfgStyle vc_getVserverCfgStyle](#) (char const *id)
- char * [vc_getVserverName](#) (char const *id, [vcCfgStyle](#) style)
- char * [vc_getVserverCfgDir](#) (char const *id, [vcCfgStyle](#) style)
- char * [vc_getVserverAppDir](#) (char const *id, [vcCfgStyle](#) style, char const *app)
- char * [vc_getVserverVdir](#) (char const *id, [vcCfgStyle](#) style, bool physical)
- [xid_t vc_getVserverCtx](#) (char const *id, [vcCfgStyle](#) style, bool honor_static, bool *is_running, [vc-CtxType](#) type)
- char * [vc_getVserverByCtx](#) ([xid_t](#) ctx, [vcCfgStyle](#) *style, char const *revdir)
- int [vc_compareVserverById](#) (char const *lhs, [vcCfgStyle](#) lhs_style, char const *rhs, [vcCfgStyle](#) rhs_style)
- void [vc_exitLikeProcess](#) (int pid, int ret)
- int [vc_createSkeleton](#) (char const *id, [vcCfgStyle](#) style, int flags)

6.2.1 Detailed Description

The public interface of the the libvserver library.

Definition in file [vserver.h](#).

6.2.2 Define Documentation

6.2.2.1 #define VC_DYNAMIC_XID (([xid_t](#))(-1))

the value which means a random (the next free) ctx

Definition at line 67 of file [vserver.h](#).

6.2.2.2 #define VC_NOCTX (([xid_t](#))(-1))

the value which is returned in error-case (no ctx found)

Definition at line 64 of file [vserver.h](#).

6.2.2.3 #define VC_SAMECTX (([xid_t](#))(-2))

the value which means the current ctx

Definition at line 69 of file [vserver.h](#).

6.2.3 Typedef Documentation

6.2.3.1 typedef uint_least64_t [vc_limit_t](#)

The type which is used for a single limit value.

Special values are

- VC_LIM_INFINITY ... which is the infinite value
- VC_LIM_KEEP ... which is used to mark values which shall not be modified by the [vc_set_rlimit\(\)](#) operation.

Else, the interpretation of the value depends on the corresponding resource; it might be bytes, pages, seconds or litres of beer.

Definition at line 554 of file vserver.h.

6.2.3.2 an_unsigned_integer_type `xid_t`

The identifier of a context.

Definition at line 349 of file vserver.h.

6.2.4 Function Documentation

6.2.4.1 `int vc_add_dlimit (char const * filename, xid_t xid, uint_least32_t flags)`

Add a disk limit to a file system.

6.2.4.2 `int vc_createSkeleton (char const * id, vcCfgStyle style, int flags)`

Create a basic configuration skeleton for a vserver plus toplevel directories for pkgmanagemt and filesystem (when requested).

6.2.4.3 `int vc_get_dlimit (char const * filename, xid_t xid, uint_least32_t flags, struct vc_ctx_dlimit * limits)`

Get a disk limit.

6.2.4.4 `tag_t vc_get_task_tag (pid_t pid)`

Get the filesystem tag for a process.

6.2.4.5 `char* vc_getVserverAppDir (char const * id, vcCfgStyle style, char const * app)`

Returns the path of the configuration directory for the given application. The result will be allocated and must be freed by the caller.

6.2.4.6 `char* vc_getVserverByCtx (xid_t ctx, vcCfgStyle * style, char const * revdir)`

Resolves the cfg-path of the vserver owning the given ctx. 'revdir' will be used as the directory holding the mapping-links; when NULL, the default value will be assumed. The result will be allocated and must be freed by the caller.

6.2.4.7 `char* vc_getVserverCfgDir (char const * id, vcCfgStyle style)`

Returns the path of the vserver configuration directory. When the given vserver does not exist, or when it does not have such a directory, NULL will be returned. Else, the result will be allocated and must be freed by the caller.

6.2.4.8 `xid_t vc_getVserverCtx (char const * id, vcCfgStyle style, bool honor_static, bool * is_running, vcCtxType type)`

Returns the ctx of the given vserver. When vserver is not running and 'honor_static' is false, VC_NOCTX will be returned. Else, when 'honor_static' is true and a static assignment exists, those value will be returned. Else, the result will be VC_NOCTX.

When 'is_running' is not null, the status of the vserver will be assigned to this variable.

6.2.4.9 char* vc_getVserverName (char const * *id*, *vcCfgStyle* *style*)

Resolves the name of the vserver. The result will be allocated and must be freed by the caller.

6.2.4.10 char* vc_getVserverVdir (char const * *id*, *vcCfgStyle* *style*, bool *physical*)

Returns the path to the vserver root-directory. The result will be allocated and must be freed by the caller.

6.2.4.11 bool vc_is_dynamic_xid (*xid_t* *xid*)

Returns true iff *xid* is a dynamic xid

6.2.4.12 *nid_t* vc_nidopt2nid (char const *, bool *honor_static*, char const ** *err_info*)

Maps a nid given at '-nid' options to a *nid_t*

6.2.4.13 int vc_rem_dlimit (char const * *filename*, *xid_t* *xid*, uint_least32_t *flags*)

Remove a disk limit from a file system.

6.2.4.14 int vc_set_dlimit (char const * *filename*, *xid_t* *xid*, uint_least32_t *flags*, struct *vc_ctx_dlimit* const * *limits*)

Set a disk limit.

6.2.4.15 int vc_tag_create (*tag_t* *tag*)

Create a new filesystem tag space.

6.2.4.16 int vc_tag_migrate (*tag_t* *tag*)

Migrate to an existing filesystem tag space.

6.2.4.17 *tag_t* vc_tagopt2tag (char const *, bool *honor_static*, char const ** *err_info*)

Maps a tag given at '-tag' options to a *tag_t*

6.2.4.18 *xid_t* vc_xidopt2xid (char const *, bool *honor_static*, char const ** *err_info*)

Maps an xid given at '-xid' options to an *xid_t*

Index

helper

- [vc_get_nb_ipv4root](#), 8
- [vc_list2bcap](#), 8
- [vc_lobcap2text](#), 9
- [vc_parseLimit](#), 9
- [vc_text2bcap](#), 10

Helper functions, 8

internal.h, 19

Mapping_uint32, 10

Mapping_uint64, 11

Syscall wrappers, 2

syscalls

- [vc_ctx_create](#), 3
- [vc_ctx_kill](#), 3
- [vc_ctx_migrate](#), 4
- [vc_ctx_stat](#), 4
- [vc_get_iattr](#), 4
- [vc_get_rlimit](#), 5
- [vc_get_task_xid](#), 5
- [vc_get_vci](#), 5
- [vc_get_version](#), 5
- [vc_getfilecontext](#), 5
- [vc_new_s_context](#), 6
- [vc_reset_minmax](#), 6
- [vc_rlimit_stat](#), 6
- [vc_set_ipv4root](#), 7
- [vc_set_rlimit](#), 7
- [vc_syscall](#), 7
- [vc_virt_stat](#), 7

[vc_add_dlimit](#) vserver.h, 30

[vc_createSkeleton](#) vserver.h, 30

[vc_ctx_caps](#), 11

[vc_ctx_create](#) syscalls, 3

[vc_ctx_dlimit](#), 12

[vc_ctx_flags](#), 12

[vc_ctx_kill](#) syscalls, 3

[vc_ctx_migrate](#) syscalls, 4

[vc_ctx_stat](#), 13 syscalls, 4

[VC_DYNAMIC_XID](#) vserver.h, 29

[vc_err_listparser](#), 13

[vc_get_dlimit](#) vserver.h, 30

[vc_get_iattr](#) syscalls, 4

[vc_get_nb_ipv4root](#) helper, 8

[vc_get_rlimit](#) syscalls, 5

[vc_get_task_tag](#) vserver.h, 30

[vc_get_task_xid](#) syscalls, 5

[vc_get_vci](#) syscalls, 5

[vc_get_version](#) syscalls, 5

[vc_getfilecontext](#) syscalls, 5

[vc_getVserverAppDir](#) vserver.h, 30

[vc_getVserverByCtx](#) vserver.h, 30

[vc_getVserverCfgDir](#) vserver.h, 30

[vc_getVserverCtx](#) vserver.h, 30

[vc_getVserverName](#) vserver.h, 31

[vc_getVserverVdir](#) vserver.h, 31

[vc_ip_mask_pair](#), 14

[vc_is_dynamic_xid](#) vserver.h, 31

[vc_limit_t](#) vserver.h, 29

[vc_list2bcap](#) helper, 8

[vc_lobcap2text](#) helper, 9

[vc_net_addr](#), 14

[vc_net_caps](#), 14

[vc_net_flags](#), 15

[vc_new_s_context](#) syscalls, 6

[vc_nidopt2nid](#) vserver.h, 31

[VC_NOCTX](#) vserver.h, 29

[vc_nx_info](#), 15

[vc_parseLimit](#)

- helper, 9
- vc_rem_dlimit
 - vserver.h, 31
- vc_reset_minmax
 - syscalls, 6
- vc_rlimit, 15
- vc_rlimit_mask, 16
- vc_rlimit_stat, 16
 - syscalls, 6
- VC_SAMECTX
 - vserver.h, 29
- vc_sched_info, 17
- vc_set_dlimit
 - vserver.h, 31
- vc_set_ipv4root
 - syscalls, 7
- vc_set_rlimit
 - syscalls, 7
- vc_set_sched, 17
- vc_syscall
 - syscalls, 7
- vc_tag_create
 - vserver.h, 31
- vc_tag_migrate
 - vserver.h, 31
- vc_tagopt2tag
 - vserver.h, 31
- vc_text2bcap
 - helper, 10
- vc_virt_stat, 18
 - syscalls, 7
- vc_vx_info, 18
- vc_xidopt2xid
 - vserver.h, 31
- vserver.h, 20
 - vc_add_dlimit, 30
 - vc_createSkeleton, 30
 - VC_DYNAMIC_XID, 29
 - vc_get_dlimit, 30
 - vc_get_task_tag, 30
 - vc_getVserverAppDir, 30
 - vc_getVserverByCtx, 30
 - vc_getVserverCfgDir, 30
 - vc_getVserverCtx, 30
 - vc_getVserverName, 31
 - vc_getVserverVdir, 31
 - vc_is_dynamic_xid, 31
 - vc_limit_t, 29
 - vc_nidopt2nid, 31
 - VC_NOCTX, 29
 - vc_rem_dlimit, 31
 - VC_SAMECTX, 29
 - vc_set_dlimit, 31
 - vc_tag_create, 31
 - vc_tag_migrate, 31
 - vc_tagopt2tag, 31
 - vc_xidopt2xid, 31
 - xid_t, 30
- xid_t
 - vserver.h, 30